

Keyboard Layout Language Spec DRAFT - 0.5c



Revision History

Date	Author(s)	Description					
2014-05-10	НааТа	Initial Draft					
2014-05-11	НааТа	Finished trigger section					
2014-05-15	НааТа	Finished result section					
2014-05-17	НааТа	Initial pass at USB Code Table					
2014-05-18	НааТа	Finished USB Code Table					
2014-09-07	НааТа	Initial KLL implementation					
2014-11-21	НааТа	Adding Defines					
2015-05-02	НааТа	Adding Media Keys and Null Key					
2015-09-29	НааТа	Adding soft replacement					
2015-10-17	НааТа	Adding more consumer control codes					
2015-05-19	НааТа	Adding key state scheduling					
2015-12-02	НааТа	Adding Pixel Output Control					
2015-12-10	НааТа	Adding array variables					
2016-04-20	НааТа	Adding trigger macro isolation					
2016-10-09	НааТа	Adding pixel addressing types					
	2014-05-10 2014-05-11 2014-05-15 2014-05-17 2014-05-18 2014-09-07 2014-11-21 2015-05-02 2015-09-29 2015-10-17 2015-05-19 2015-12-02 2015-12-10 2016-04-20	2014-05-10 HaaTa 2014-05-11 HaaTa 2014-05-15 HaaTa 2014-05-17 HaaTa 2014-05-18 HaaTa 2014-09-07 HaaTa 2014-11-21 HaaTa 2015-05-02 HaaTa 2015-09-29 HaaTa 2015-10-17 HaaTa 2015-10-17 HaaTa 2015-12-02 HaaTa 2015-12-02 HaaTa 2015-12-10 HaaTa 2016-04-20 HaaTa					

Contents

1	Summary	. 1
2	Scope	. 1
3	Variables	. 2
	3.1 Defines	. 2
4	Capabilities	. 3
5	Keymapping	. 4
	5.0.1 Isolation	. 5
	5.1 Trigger	. 6
	5.1.1 Sources	. 7
	5.1.2 Scan Code	. 7
	5.1.2.1 State Scheduling	. 8
	5.1.2.2 Key Positioning	. 8
	5.1.3 USB Code	. 9
	5.1.3.1 State Scheduling	. 10



		5.1.3.2 Analog States
		5.1.4 LED Indicator Code
		5.1.4.1 State Scheduling
		5.1.5 Range
		5.1.6 Sequence
		5.1.7 Combination
		5.1.8 Timing
	5.2	Result
		5.2.1 USB Code
		5.2.1.1 State Scheduling
		5.2.2 None
		5.2.3 Consumer Control Code
		5.2.4 System Control Code
		5.2.5 Sequence
		5.2.6 Combination
		5.2.7 Capability
		5.2.8 Timing
6	File	e Format
	6.1	Comments
	6.2	Required Variables
	6.3	Layer Control
	6.4	Example Keymap
7	Lay	ering
	7.1	Scan Map
	7.2	Combined Map
	7.3	Partial Map
8	Pix	el Output Control
		Pixel Mapping
	8.2	Animations
		8.2.1 Pixel Addressing
	8.3	Triggers
	8.4	Results
	8.5	Pixel Positioning



9	Compilation											29
10	USB Code Table											31
11	System Control Code Table											38
12	Consumer Control Code Tabl	e										40
13	LED Indicator Code Table											49
14	Capabilities Table											5 2
15	Glossary											5 3
16	Future Considerations											54
	16.1Possible 0.6+											54



1 Summary

This document outlines a complex keymapping scheme for custom keyboard firmware. It is based upon the concept of trigger:result pairs and ways to configure both parts of the pair (input and output). A variety of macros are supported along with analog keyswitches.

In addition, this keymapping scheme supports static and dynamic layering as well as supporting arbitrary keyboard features that may or may not be available on a given keyboard.

2 Scope

Hardware keymappings for keyboards traditionally has been cumbersome. At best, each layer can be defined as a set of predefined trigger:result pairs. A trigger being a key and a result being a key press (e.g. USB Code). Some keyboards allow for macros; however, these macros usually have to be custom programmed to the microcontroller (most, if not all custom keyboard firmware), or have very limited scope (Kinesis Advantage Pro and some Cherry POS keyboards such as the G80-8200).

Secondly, keymap layering (e.g. FN Layer) almost universally supports distinct layers (in the firmware that support this). However, no current firmware support "partial layering". Partial layering is only modifying a part of the current layout, similar to how XKB handles remapping Ctrl and CapsLock.

To reduce size constraints, EEPROM storage of keyboard layouts will not be considered. It may be possible to do post compilation keymap modifications, but this is considered optional for an implementation.

Finally, as of current (2015-05-10), no keymapping mechanism supports analog keyswitches for use in typing. This is mostly lack of availability of analog keyboard switches.



3 Variables

Variables serve two purposes. The first, to give information to the compiler both for informational and controlling internal keyboard firmware features. The second is for keymapping convenience. In most cases variables will only be used for compiler information.

Variables used for non-compiler purposes must be integers. The compiler will enforce this.

Variables are defined as follows.

```
<variable name> = <contents>;
```

Each command ends with a semi colon, there are no exceptions to this. Every keymap file will have the following variable.

```
Name = myKeymapFile;
```

If spaces are required for either the variable name or variable contents, doubles quotes may be used. The spaces will be internally converted to underscores if the variable is used for non-informational purposes. Variable names can only use A-Z, a-z, 0-9 and underscores and must not start with a number.

```
"space containing variable" = "space-ful variable";
mix = "And Match";
```

In some cases it's necessary to define an array variable to give the compiler better context of the variables. Particularly when defining separate buffer locations that need to be combined into a single index range (e.g. Pixel Control). Arrays can be defined by index or space separated list. If the compiler is unsure about how to use the array it will default to a space separated list as the output (e.g. Defines).

```
variable[0] = "index 1 info";
variable[1] = 56;
var2[] = item1 item2 "item 3";
```

3.1 Defines

Defines are a special case of variables that are used to influence static configuration options of the keyboard. This allows information to be given to the keyboard firmware before it is compiled. For example, defining the



word size of the macro definition (i.e. using 8 bit instead of 32 bit when only 256 positions are required).

Defines are set the same way as variables are. However, and additional configuration is required to indicate which variables set defines for the compiled firmware. This help save the user from not setting critical defines that the firmware requires as warning messages are generated by the compiler when they are missing.

```
<capability name> => <corresponding C/C++ define>;
```

Each keyboard will likely have a different set of configurable defines which will be exposed. By default, they will have set values; however, these values can be overridden.

```
# Define declaration
myDefine => myCDefine;

# Default value
myDefine = 23;

# Override
myDefine = 144;
```

In order to pass strings, the desired quotes must be double-quoted.

```
myDefine => myCDefine;

# Correct
myDefine = '"This is a good string"';

# Possibly incorrect
myDefine = "This is an iffy string";
```

The second variable assignment will not pass the double quotes to the generated file so the result will not be interpreted as a C-String by the C/C++ compiler.

4 Capabilities

Capabilities define what the keyboard can do. At basic level, each keyboard has the capability to send USB Codes. Some keyboards have solenoids



that can be fired, others have clickers. Capabilities are read by the compiler to cross-reference the functions that control that capability to the designated key press.

If a capability is specified as a result to a keypress and is not defined for the specified keyboard, it is ignored and removed from the compiled keyboard mappings (for each of the layers it is defined on).

In general, capabilities specific to each keyboard are defined in the keyboard specific Scan Code to USB Code keymap. Capabilities such as clickers and solenoids are defined using a standard so that their functionality does not have to be redefined for each keymap (i.e. keymaps are transferable between keyboards even with special functionality that does not apply to every keyboard).

Capabilities are defined as follows.

```
<capability name> => <corresponding C/C++ function>;
```

The arguments of the C/C++ function must be specified, but not defined. Capabilities are used to describe to both the compiler and user, what the special functionality is supposed to do. The argument names themselves should be descriptive names containing no spaces, start with a letter and may use a-z, A-Z, 0-9 and underscore. The colon after each argument specifies the byte length of the argument. This number must be an positive integer.

Capabilities have two implied arguments, state and state type. These arguments are set by the TriggerMacro that signaled this Capability.

```
# Correct
myCapability => myCFunction( arg1:1, arg2:2 );
# Incorrect, defines the arg2 as 25
yourCapability => myCFunction( arg1:1, 25:2 );
```

Refer to Section 14 for a list of common capabilities.

5 Keymapping

Keymapping is the main purpose of KLL. KLL is designed to deal with most kinds of macros and layering (in addition to keyboard specific functions). Keymapping is defined in two parts. The first part is call the trigger. The



trigger defines what the signal of a keypress (e.g. press a) is that will be used to generate a result (e.g. send USB Code a). Triggers can be simple or very complex. Defined as Scan Codes (non-portable) and USB Codes (portable).

The second part is called a result. The result is what the keyboard firmware is designated to do once the corresponding trigger is received. Results vary from sending single USB Codes, to USB Code Macros, to enabling keyboard specific capabilities and toggling other keymapped layers. Defined as USB Codes and Capabilities. If an undefined Capability is used it is ignored and the trigger:result pair is removed from the keymap.

As a note, time based key sequences (e.g. entering keys within a specified period of time) are not supported for both the trigger and result mechanisms. These may be added in a future version of KLL if enough demand (and a sensible/scalable implementation is proposed).

The following is the general syntax of the trigger:result pair.

```
<trigger> : <result>;
```

There are four variants of the trigger:result pair. Depending on which variant is used, assignment of the result changes.

```
<trigger> : <result>; # Replaces results on trigger
<trigger> :: <result>; # Soft layer replacement
<trigger> :+ <result>; # Adds results to trigger
<trigger> :- <result>; # Removes result from trigger
```

In general, the normal trigger:result pair will be used to replace/change keymapping. The trigger::result pair is a soft layer replacement which is used to only do replacement if two conditions are met: not the default layer and the trigger being replaced is not the same as defined in the base map. This is useful for making broad replacement rules for all layers but only come into effect if actually being used. An adding trigger:+result pair is useful when adding an extra action to a key of macro of keys (e.g. solenoid press). A subtraction trigger:-result pair is useful when compiling in many layouts and there are certain additions that are undesirable.

5.0.1 Isolation

Sometimes it's useful to define macros that are comprised of simple macros already linked to results. Instead of using the more sophisticated state scheduling in Section 5.1.2.1, trigger assignment isolation can be



used. For example, say the A and B keys are already assigned to output 'A' and 'B' respectively. However, you want A+B together to output 'Q', but not 'A' or 'B'. Isolation macros, when triggered will cancel any other macros that may be active or may activate during that processing loop. This means if you pressed A, then B, 'A' then 'Q' will be displayed. And if you keep holding down B and A, then 'Q' will start repeating. If A is released, then 'B' will output. So, to just output 'Q' both A and B must be pressed then released during the same scan cycle.

```
<trigger> i: <result>; # Replaces results on trigger
<trigger> i:: <result>; # Soft layer replacement
<trigger> i:+ <result>; # Adds results to trigger
<trigger> i:- <result>; # Removes result from trigger
```

If more than one isolation trigger is activated at the same time the behaviour is undefined and any one of the isolated triggers may take priority depending on how the firmware processes the inputs.

5.1 Trigger

The trigger defines the conditions required for a specific keymapping. These conditions can be as simple as a single key press or as complex as sequences of key combinations.

A trigger is defined for each type of source. For a keyboard, the source types are Scan Codes and USB Codes. Other types of source types include axis control (mouse), rotation control (mouse wheel), indicator codes (keyboard lock lights).

Beyond this, it is possible to specify ranges of sources to do the same function. Require a sequence of sources entered to enable a function. Use a combination of sources to trigger a capability.

For each type of source a state may be used to control what the trigger of the source is. With analog switches it's possible to define a percentage value threshold for a key.

Precedence is evaluated as follows: Scan Code/USB Code/Source then range, then combination and finally sequence. Ranges of combinations does not make sense, nor does combinations of sequences.



5.1.1 Sources

A source is a control interface that generates a change in state that, using a measure or threshold that can trigger an event. For keyboards, Scan Codes are native identifiers to the keyboard firmware. Whereas USB Codes are the identifiers used to send over USB to the OS. After compilation, all keymappings are mapped to Scan Codes; however, using Scan Codes in keymap files is not portable between different keyboards so their use is discouraged outside of defining the default Scan Code to USB Code keymap.

Logical mappings are not used for other types of control such as axis control, rotation control and indicator codes.

5.1.2 Scan Code

Scan Codes are the native identifier for keypresses on keyboard firmware. In general, Scan Codes should not be used for defining keymaps; however, they are required for defining the initial Scan Code to USB Code mapping for each keyboard.

Each trigger must identify whether it is a Scan Code or USB Code. For Scan Codes it is prefixed with an S.

```
S<Scan Code> : <result>;
```

Scan Codes can be defined as either hex or decimal numbers.

```
S0x2A : <result>;
S124 : <result>;
```

The compiler will error if it is specified in the keymap explicitly.

For keyboards that are interconnect capable, it is possible to set the interconnect index for that keyboard. By default, a scan code is defined as index 0. This can be changed using the **ConnectId** variable. This variable is effective immediately.

```
S0x2A : <result>; # Defaults to index 0
ConnectId = 2;
S0x2A : <result>; # Defaults to index 2
S124 : <result>; # Also defaults to index 2
```



5.1.2.1 State Scheduling

Instead of processing the trigger immediately, as done by default, it is also possible to put additional state conditions on the keypress. Keyswitch trigger events have 6 different states that can be specified: press (\mathbf{P}) , hold (\mathbf{H}) , release (\mathbf{R}) , off (\mathbf{O}) , unique press (\mathbf{UP}) and unique release (\mathbf{UR}) . State conditions are defined using parenthesis after the keyswitch definition.

The press event is the default schedule event for keyswitches. The release event is useful for signalling an event after the key has been released rather than when it was pressed. Unique press is a special state that requires no other keyswitch is currently in the press or hold state. Unique release is another special state requiring no additional keypresses since this key was pressed. This is often referred to as "tap" keys.

```
S100 : <result>;
S100(P) : <result>; # Same as above
S101(UP) : <result>; # Tap key
S102(UR) : <result>; # Single key input
S103(R) : <result>; # Single-shot on release
```

Hold and off are non-triggering events so they cannot be used to trigger results alone. This means they **must** be part of a combination with a triggering event (see Section 5.1.7).

```
S104(H) : <result>; # Incorrect
S104(H) + S105(O) : <result>; # Incorrect
S100 + S104(H) : <result>; # Correct, holding a key
S101 + S105(O) : <result>; # Correct, key is not pressed
```

5.1.2.2 Key Positioning

It is possible to give a physical location to a particular Scan Code. This allows for configuration utilities to automatically generate the layout as well as give hints to pixel positioning (i.e. backlight keys). Key positioning is generally completely optional and needs to be done once for every physical layout configuration of the device.

Each key may be assigned the following options, by default they are set to 0.

• x, y, z positions (mm)



• rx, ry, rz rotations (deg)

The units are in mm and degrees respectively.

```
# Set the x position 20 mm and x rotation 15 deg
$120 <= x:20,rx:15;</pre>
```

Currently keycap shape is not supported. Though suggestions are welcome on how best to support them (especially the odd shaped ones).

5.1.3 **USB Code**

USB Codes define how USB understands keyboard output press/release events and are defined by the USB HID Spec. USB Codes are the recommend identifier when defining triggers for KLL keymaps.

Each trigger must identify whether it is a Scan Code or USB Code. For USB Codes it is prefixed with a U.

```
U<USB Code> : <result>;
```

USB Codes can be defined in a number of ways. Like Scan Codes, the USB Code can be defined directly using hex or decimal numbers (not recommended). The recommended way is to use the descriptive names for the USB Codes. Descriptive names are always strings, and must be enclosed with double quotes.

```
U0x2A : <result>;
U124 : <result>;
U"A" : <result>;
U"a" : <result>; # Same as previous
```

Refer to Section 10 for the complete list of USB Codes.

There is an important difference when using a USB Code as the the Trigger as compared to a Scan Code. When an assignment is done using a USB Code, a lookup must occur to find the original Scan Code that the USB Code was assigned to. Since assignment order matters this can become confusing.

```
U"s" : U"r";
U"r" : U"p";
```

This has an unintended side-effect. All R's will be assigned to P. If the user is aware, the problem isn't too bad to deal with. However, this is



a very tricky problem to deal with for GUI keymap programs as it is not intuitive to enforce order.

Therefore, to resolve this issue, all assignments using a USB Code trigger must be cached until the current kll file has finished parsing. Then the cached assignments can be applied to the current layer. This will allow mass assignment of keys without having to worry about the order of assignment. If re-assignment is needed, use another kll file or a Scan Code trigger.

5.1.3.1 State Scheduling

All of state schedulers used for Scan Code triggers are applicable for USB Code triggers (see Section 5.1.2.1).

```
U"A" : <result>;
U"A"(P) : <result>; # Same as above
U"B"(UP) : <result>; # Tap key
U"C"(UR) : <result>; # Single key input
U"D"(R) : <result>; # Single—shot on release
U"A" + U"Q"(H) : <result>; # Correct, holding a key
U"B" + U"W"(O) : <result>; # Correct, key is not pressed
```

5.1.3.2 Analog States

For analog keyboard switches, it is useful to specify a trigger at a press percentage as press/release behaviour needs to be defined. The expected implementation defines a press when the key stops moving or begins to move back up. If a stopped key moves further down (past the next trigger), stops or begins to move back up the next trigger is used and the previous on is released. Again, if the stopped key moves back up going back over a past trigger, stops (or with a slight delay before going back up further) this past trigger will activate, releasing the previous trigger.

Analog triggers are specified using parenthesis.

```
<Code>(<Analog Value>) : <result>;
```

Both USB Codes and Scan Codes can be used with analog keyboards signals. Mapping analog triggers gets more tricky, so it is recommended that they are only used with USB Codes. Analog triggers are specified from 0 to 100 using integers only. 0 is a special case and is only pulsed



when it is reached rather than held.

```
S0x2A(10) : <result>; # 10% press

S0x2A(80) : <result>; # 80% press

U124 (50) : <result>; # 50% press

U"A" (0) : <result>; # 0% pulse

U"a" (52) : <result>; # 52% press
```

If the keyboard is not analog, any trigger with an analog trigger will be ignored. And inversely, if the Scan Code/USB Code maps to an analog key, a normal press/release trigger will be ignored.

5.1.4 LED Indicator Code

Instead of using a keypress as the trigger to a macro, it is also possible to use the state of a HID LED Indicator such as Caps Lock.

```
I<Indicator Code> : <result>;
```

Indicator codes can be specified using a numeric or string identifier.

```
U"a" + I2 : <result>; # a + CapsLock
U"a" + I0x3 : <result>; # a + ScrollLock
U"a" + I"NumLock" : <result>; # a + NumLock
```

Refer to Section 13 for the complete list of LED Indicator Codes.

5.1.4.1 State Scheduling

Similar to keypresses, indicator codes have four states: activate (**A**), on (**On**), deactivate (**D**) and off (**Off**). Also similar to keypresses, on and off cannot be used to trigger a macro. While activate and deactivate can be used as a trigger to a macro. The default state for LED Indicator codes is activate.

```
I"NumLock" : <result>;
I"NumLock"(A) : <result>; # Same as above
I"NumLock"(D) : <result>; # NumLock disable
```

The on and off states must be specified with another trigger as they are non-trigger conditions.

```
I"NumLock"(On) + U"c" : <result>; # Correct
U"a" + I"NumLock"(Off) : <result>; # Correct
```



```
| I"NumLock"(Off) : <result>; # Incorrect | r"NumLock"(On), U"d" : <result>; # Incorrect
```

Keep in mind that the LED Indicator Codes are controlled by the host OS and not by the keyboard. There is always the chance that the OS tries to do something strange with the LEDs that may not match what the OS itself is doing (i.e. CapsLock led is off, but all keys are outputing as caps). In this case there is really nothing the keyboard can do to right itself.

5.1.5 Range

For convenience, it is also possible to define a range of triggers rather than explicitly defining each of the trigger:result pairs. This is useful for defining things such as using the clicker speaker for every single key or just the letter keys.

Ranges are defined as the numerical range of either USB Codes or Scan Codes (use not recommended). Fortunately this means ranges such as A-Z will work has USB HID defines the USB Codes in order. Unfortunately the range 0-9 will not work as the USB Codes are organized: 1, 2, 3, 4, 5, 6, 7, 8, 9, 0 just like on a keyboard. To assist with this problem, the compiler will warn when this situation occurs. Forward and reverse ranges are possible. There is no wrap-around. Scan Codes and USB Codes cannot be mixed.

To define a range, two additional pieces of syntax are required: square brackets and range specifier.

```
S[0x2A-0x50] : <result>;
S[12-43] : <result>;
S[69] : <result>; # Also a valid definition
U[124-43] : <result>; # Reverse range
U["A"-"Z"] : <result>;
U["0"-"9"] : <result>; # Compiler will warn, only 0 and 9
U["1"-"0"] : <result>; # Correct definition of 0-9
```

In addition to a specific range, multiple single keys or ranges may also be specified.

```
S[0x2A-0x50, 0x5] : <result>;
S[12, 43] : <result>;
U["A"-"Z", "Enter"] : <result>;
```

When using an analog supporting keyboard, a range is specified to that specific range. Or the analog trigger can be specified for the entire range.



```
S[0x2A-0x50(20), 0x5(56)] : <result>;
S[12, 43](79) : <result>;
U["A"-"Z"(42),"Tab"](30) : <result>; # 30, unless specified
```

5.1.6 Sequence

Sequences are a type of macro. A sequence is a set of expected inputs that must happen in order with no extra inputs of non-defined inputs. If a non-defined input is found, the sequence is reset and waits for the first input in the sequence again. Sequences cannot mix Scan Codes and USB Codes.

Trigger inputs in the sequence are separated by commas. The Scan Codes and USB Codes are evaluated/expanded first, then the sequences are evaluated (Codes have higher precedence).

```
S[0x2A-0x50], S[12], U[5] : <result>; U["Q"-"Y"], U["Enter"] : <result>; U["A"-"Z"(42),"Tab"](30), U[12](53) : <result>;
```

Analog triggers cannot be set across multiple inputs in the sequence.

For convenience, a second sequence syntax is available only for specifying ASCII characters. This allows for sentences to be inputted rather than the individual USB Codes. The key difference is the use of single quotes. If a shift is required for the specific key, it will be added as a combination (see Section 5.1.7).

```
'abc' : <result>;
U'T' : <result>;
U['Can you type this?'](23) : <result>;
```

Single quotes are only used for sentence expansion, they cannot be used for strings.

5.1.7 Combination

Combinations are a type of macro. A combination is a set of inputs pressed at the same time. For example: Ctrl+Alt+Delete. In order for a combination trigger to be signalled all of the keys must be pressed. The combination will not end if a key is missing from the combination (as the user may not have pressed it yet). Extra keys not part of the com-



bination also do not cancel the combination. Combinations cannot mix Scan Codes and USB Codes.

Trigger inputs in the combination are separated by pluses. The Scan Codes and USB Codes are evaluated/expanded first, then sequences are evaluated and finally combinations (Codes have the highest precedence, then sequences, then combinations).

```
U["Q"-"Y"] + U["Enter"] : <result>;
S[0x2A-0x50] + S[12], U[5] : <result>;
U["A"-"Z"(42),"Tab"](30) + U[12](53) : <result>;
'Can you type this?'(23) + 'a'(43) : <result>;
```

Analog triggers cannot be set across multiple inputs in the combination.

5.1.8 Timing

It is possible to assign a time to a given trigger. This allows for sophisticated time based input sequences.

The granularity of the fundamental time base depends on the hardware. This time base is advertised by the underlying hardware to the KLL compiler using the **timeBase** define.

The following are the accepted time units.

- s Seconds
- ms Milliseconds
- **us** Microseconds

Fractional numbers are also valid (e.g. 1.43 s). If the number will be rounded to the nearest fundamental time unit. Avoid using the fundamental time unit directly as it will not behave the same way between different keyboards.

The format is as follows.

```
<identifier>([<state scheduler>][:<time>]) : <result>;
```

Hold A for at least 300 ms.

Hold A for at most 300 ms.



```
U"a"(R:300ms) : <result>;
```

More complicated state scheduling is also possible. Press timers may be used to have combos that require a key pressed first then after a certain amount of time another key must be pressed, which then completes the element in the sequence.

Non-trigger events cannot be used with a time specifier. This includes: **On**, **Off** and **Hold**. Hold can only be used when using multiple time triggers.

Multiple time triggers may be used to define more complex input sequences. For example, to press A, require a wait time of 50 ms then hold for at least 100 ms, but no longer than 200 ms.

```
U"a" + U"b"(P:50ms, H:100ms, R:200ms);
```

5.2 Result

The result is the action, or set of actions, after the conditions for the trigger have been satisfied. The result can be as simple as a single USB Code output or as complex as signalling a keyboard specific clicker and outputting a combinational macro. A Scan Code cannot be used as a result.

Like triggers, there are two basic types of results: keyboard specific functionality and USB Codes. Both of these results are referred to as capabilities. A basic capability of every keyboard is to send USB Codes, while other keyboards may have other capabilities such FN layers or clickers. When a trigger is satisfied each of the results assigned to this trigger are signalled.

Much of the syntax is the same as with triggers. The major difference being, no analog qualifiers and no ranges. Some state scheduling qualifiers also may not apply in all situations, if at all.



5.2.1 **USB Code**

USB Codes are the primary use of the result part of the trigger:result pairs. Result USB Codes are defined the same way as trigger USB Codes (Section 5.1.3).

```
<trigger> : U0x2A;
<trigger> : U124;
<trigger> : U"A";
<trigger> : U"a"; # Same as previous
```

Refer to Section 10 for the complete list of USB Codes.

5.2.1.1 State Scheduling

It is also possible to schedule output sequences just as with USB Code triggers (see Section 5.1.3.1). Result USB Codes have three scheduling types: press (\mathbf{P}), hold (\mathbf{H}) and release (\mathbf{R}). Off, unique press and unique release have no meaning for output and therefore are not available. The hold state can only be used with a timing specifier (see Section 5.2.8).

By default, the press specifier is used and the key is released before the next sequence element and/or the end of the sequence.

```
<trigger> : U"A";

<trigger> : U"A"(P,R); # Same as previous

<trigger> : U"A"(P), U"A"(R);

<trigger> : U"A"(P); # Does not release a

<trigger> : U"A"(R); # Only releases a if active/pressed
```

5.2.2 None

Sometimes it is useful to block the fall-through to a previous layer and have the key do nothing. The **None** keyword is case sensitive.

```
<trigger> : None;
```

5.2.3 Consumer Control Code

Consumer Control Codes, or Media Keys are a USB HID control type that allows you to control media functions. These include global hotkeys such



as Play, Next and Previous.

Similar to USB Codes (Section 5.1.3), Consumer Control Codes can be defined as numbers or by its symbolic name. It is important to note that there is no support for sequences, combinations or ranges of Consumer Control Codes.

```
<trigger> : CON0xB0;
<trigger> : CON176;
<trigger> : CON"Play";
<trigger> : CON"play"; # Same as previous
```

Refer to Section 12 for the complete list of Consumer Control Codes.

Consumer Control Codes may also use state scheduling. See Section 5.2.1.1 for usage details.

5.2.4 System Control Code

System Control Codes are a USB HID control type that allows you to system level functions. These include global hotkeys such as Power, Sleep and Eject.

Similar to USB Codes (Section 5.1.3), System Control Codes can be defined as numbers or by its symbolic name. It is important to note that there is no support for sequences, combinations or ranges of System Control Codes.

```
<trigger> : SYS0x82;
<trigger> : SYS130;
<trigger> : SYS"Sleep";
<trigger> : SYS"sleep"; # Same as previous
```

Refer to Section 11 for the complete list of System Control Codes.

System Control Codes may also use state scheduling. See Section 5.2.1.1 for usage details.

5.2.5 Sequence

A result sequence is a series of outputted USB Codes which are split between each USB output buffer refresh. This is similar to a trigger input sequence. The syntax is the same as trigger sequences (Section 5.1.6.

```
<trigger> : U["Q"-"Y"], U["Enter"];
<trigger> : U["A"-"Z","Tab"], U[12];
```



Single quoted strings will be literally evaluated. Any characters requiring a Shift key will have it added as a combination as part of the result.

```
<trigger> : 'abc';
<trigger> : U'T';
<trigger> : U['Can you type this?'];
```

5.2.6 Combination

A result combination is a set of keys sent out during the same USB output buffer. The syntax is the same as trigger combinations (Section 5.1.7. Keep in mind, if the keyboard does not support NKRO then some result combinations will not be possible.

```
<trigger> : U["Q"-"Y"] + U["Enter"];
<trigger> : U["A"-"Z","Tab"] + U[12];
<trigger> : 'Can you type this?' + 'a';
```

5.2.7 Capability

In addition to outputting USB Codes, capabilities can be triggered. Technically, outputting USB Codes is a capability of the keyboard, but it is always considered to exist. If a capability is specified as a result, but is not available for that keyboard, the trigger:result pair is ignored by the compiler and removed from the keymap.

To specify a capability as the result, define the capability name and any arguments required for the capability. To use the default parameter for an argument, set the argument as NULL.

```
# Defined capability
myCapability => myCFunction( arg1:1, arg2:1 );
# Using default first argument, and 25 for the second
<trigger> : myCapability( NULL, 25 );
```

To specify one of the arguments as the analog/press (press, hold, release) variable from the trigger, specify the argument as "output".

```
# Defined capability
myCapability => myCFunction( arg1:1, arg2:1 );
```



```
# output specifies the analog/press result
<trigger> : myCapability( NULL, output );
```

Refer to Section 14 for a list of common capabilities.

5.2.8 Timing

Similar to triggers, timing may also be used for sophisticated output sequences. See Section 5.1.8 for detailed background on timing units and fundamental time steps.

The format is as follows.

```
<trigger> : <identifier>([<state scheduler][:][<time>]);
```

To press A for 300 ms.

```
<trigger> : U"a"(300ms);
<trigger> : U"a"(P,H:300ms,R); # Same as above
```

To press A after 20 ms, hold for 300 ms, then release 5 ms later.

```
<trigger> : U"a"(P:20ms,H:300ms,R:5ms);
```

Implementations will most likely not support result macro stacking/queuing. If the timing is too long, any more triggers of the result macro will likely be ignored until the original trigger result completes.

It is also possible to schedule capabilities as well. While capabilities will accept different states (Press, Hold, Release) the capability may ignore that specification depending on how it was implemented. The only part guaranteed is that at each scheduled event the capability will be called with the given state information. If a state is scheduled and the trigger input has an analog value (or other trigger specific value) associated with it that value will be discarded. This means that the output will no longer be analog and be handled as a toggle mechanism.

```
# Defined capability
myCapability => myCFunction( arg1:1, arg2:1 );

# output specifies the analog/press result
# Analog context is discarded
<trigger> : myCapability( NULL, output )(P, H:300ms, R);
<trigger> : myCapability( NULL, output )(100ms);
```



6 File Format

The Keyboard Layout Language or KLL uses a series of plain text, readable files to define configurations. This does not preclude GUI keymapping tools as it can generate KLL files first.

Each file represents a single keymapping layer and it is up the firmware configuration to define the precedence of each layer. KLL uses the concept of "Capabilities" to define potential results of a keypress (Section 4). At a basic level these are the keycodes (USB Codes) sent out to USB, but can be things like a clicker speaker or special LED signals.

6.1 Comments

End-of-line comments are defined using a '#'. For example,

```
# This is a comment
Not a comment # But this is a comment
```

defines the two supported styles of comments. Block and inline comments are not supported.

6.2 Required Variables

Each keymap file has a set of required variables that must be defined.

```
# Name of the keymap
Name = myKeymap; # Spaces will be replaced with _'s

# Version of the keymap
Version = 1.32a-HaaTa;

# Modified Date
Date = 2014-05-10;

# Author

# Multiple authors should be comma separated with the year

# range of their contributions

# Quotes can be used if spaces are required.
Author = "HaaTa (Jacob Alexander) 2014";

# KLL Version, used to detect future incompatibilities
```



```
KLL = 0.1;
```

The **Name** and **KLL** variables are used by the KLL compiler. Name prefixed to all keymap specific capabilities (e.g. myKeymap_Latch). KLL is for version checking to deal with future potential issues.

The rest of the variables are just informational. But are to be propagated to combined keymaps.

6.3 Layer Control

While up to the compiler how layers are controlled, these are some guidelines on how to control layers. Each layer must support three different activation types.

- Shift Enables keymap while held
- Latch Enables keymap until the next key is pressed
- Lock Enables keymap until Lock is pressed again

6.4 Example Keymap

The following is a QWERTY/US ANSI to Colemak keymap. Only USB Codes are used as this is not a Scan Map.

```
Name = colemak;

Version = 0.1;

Author = "HaaTa (Jacob Alexander) 2014";

KLL = 0.2a;

# Modified Date

Date = 2014-05-17;

# Top Row

'e' : 'f';

'r' : 'p';

't' : 'g';

'y' : 'j';

'u' : 'l';

'i' : 'u';

'o' : 'y';
```



```
'p' : ';';

# Middle Row
's' : 'r';
'd' : 's';
'f' : 't';
'g' : 'd';
'j' : 'n';
'k' : 'e';
'l' : 'i';
';' : 'o';
# Bottom Row
'n' : 'k';
```

When remapping ASCII characters, using single quotes is the simplest way to map keys. Remember, all other keys must be remapped using either the USB Code or USB Code identifier.

```
Name = capslock2ctrl;

Version = 0.1;

Author = "HaaTa (Jacob Alexander) 2014";

KLL = 0.2a;

# Modified Date

Date = 2014-05-17;

U["CapsLock"] : U["Ctrl"];
```

7 Layering

While the KLL files have little to do with the keymap layering implementation, there are a few features that do help with the implementation. In general, keymaps are defined by USB codes and not Scan Codes as Scan Codes are keyboard specific. However, for each keyboard an initial mapping must be defined from Scan Codes to USB Codes.

After compilation, each keymap is reduced down to Scan Codes as they are the unambiguous internal key indications that keyboard firmwares



understand.

7.1 Scan Map

The Scan Map is the keymapping used to define each type of keyboard. This keymapping must used Scan Codes to USB Codes, otherwise later compilation process will fail (as it won't be possible to resolve the Scan Codes).

If possible, each Scan Map should define a US ANSI-like keymap. Any keys that are not defined by the general US ANSI standard should be defined to another reasonable USB Code.

The scan map should also define any capabilities that are provided by the keyboard. For example, a clicker speaker.

```
# Clicker speaker with "sound select" and volume args
myControlableClicker => clickerCFunction(sound:2, volume:1);
# Use the capability when Scan Code 0x2C is pressed
# NULL specifies the default option of the capability
S[0x2C] : myControlableClicker(NULL, 25);
```

When defining capabilities like solenoids and clickers, follow the naming convention and same number of arguments. If there are extra capabilities for this keyboard (e.g. click volume), add an additional capability to control this functionality.

Refer to Section 14 for a list of common capabilities.

7.2 Combined Map

The Combined Map is a set of keymaps that have been folded (or compiled) down to a single keymap. For example, if there is the default Scan Map and a Colemak keymap is specified, both of these keymaps will be compiled down to Scan Code triggers and the USB code results (as well as any other specified capabilities). For keys that were not specified in the secondary maps (the highest layered map takes precedence) it will use the lower layer keymapping to be included into the Combined Map.



7.3 Partial Map

A Partial Map is a keymap that may not define every possible Scan Code. Some uses for Partial Maps are to swap Caps Lock and Control, or define Colemak, where not all of the keys change from QWERTY/US ANSI. Partial Maps can be used to generate a Combined Map or be compiled individually to be layered on the keyboard firmware dynamically for FN layers.

8 Pixel Output Control

Some keyboards have large arrays of pixel devices such as RGB backlighting or LCD displays. Pixel output control defines ways to specify animations and events directly using KLL without having to program custom capabilities.

Instead of triggering individual pixels, events are characterized as animation groups. These animation groups can both a trigger and a result in order to link together animation groups with complex input sequences.

As with Scan Codes/USB Codes individual pixels also need a common way to map actions to them. However, unlike Scan Codes, keyboards may have multiple disjunct sets of numbering schemes with different bit widths for controlling each pixel. To get around this a pixel mapping is required in order to teach the KLL compiler where the pixels are.

8.1 Pixel Mapping

Individual pixels such as LEDs or LCD pixels are not defined uniformly in hardware, especially if multiple types of hardware drivers are used in a single input device. To get around this logical pixels are defined that may contain multiple lighting channels. For convenience, these pixels are also mapped to Scan Codes at the same time (if relevant).

The initial channel number is hardware specific and doesn't have to be in order. While the pixel number is arbitrary and may be any number you like (stick with lower numbers for ideal packing).

```
# Format
P[<pixel>](<ch 1>:<width>, ...) : <Scan Code>;
```



```
# Pixel 5, Channel 30, Single channel
# 8 bit width, Scan Code 0x13
P[5](30:8) : S0x13;

# Pixel 6, Channels 35-37, Triple channel
# 2 bit width, Misc Pixel
P[6](35:2, 36:2, 37:2) : None;
```

8.2 Animations

Animations are sets of changes applied to one of more mapped pixels over a period of time. Values may be applied to single or sets of pixels by various means including setting, adding, subtracting, etc. For convenience pixels are automatically grouped into layers if Scan Codes were used during the pixel mapping.

Each animation is given a label. A label is an arbitrary text label (KLL string rules apply) used by KLL to identify the animation set.

```
A[<label>] <= <modifiers>;
A[MyEyesAreBleeding] <= <modifiers>;
```

While defining the animation label, default animation modifiers can be applied. Modifiers can include options such as the number of loops to run the animation, clock divider for animation speed or special hardware features the pixels may have (e.g. hardware fade).

The following modifiers are supported.

```
loop:<num> # Specific number of loops
dool
         # Loop infinitely
div:<num> # Animation frame divider
         # Stop animation(s)
start
stop
interp:<type>
          # Interpolate between channels
          # on
          # off (default)
           # kll (pre-compute interpolation,
                  fastest
          #
                  cannot be set dynamically)
frame:<frame>
```

An example modifier setup for an animation.



```
# At keyboard start, loop animation 3 times
A[MyEyesAreBleeding] <= start, loop:3;</pre>
```

Using the defined logical pixels, each frame of the animation can be defined. It is also possible to use ranges and pre-defined layers as groups of pixels within an animation set as a single colour. When sets contain heterogenious sets of number of channels (e.g. RGB vs. monochrome) the first channel operations are used first and the extra are ignored for affected pixels.

Pixel values are changed using operator:value pairs. The operator, if defined, indicates that the defined value modifies the current value rather than just overriding it. When evaluating the animation stack, the stack is parsed top to bottom until a set (no operator) value is found. This value is applied, then the above animations for that pixel are applied bottom to top.

The following operators are supported.

Each frame of the animation must be defined individually describing what changes each frame makes to which pixels. One or more pixels may be assigned to that animation frame. It's also possible to use pixel groupings and ranges of pixels.

```
# Basic animation frame syntax
A[<label>, <frame>] <= <pixels>;
# Animation "Bleed", frame 2
A[Bleeed, 2] <= <pixels>;

# Single pixel syntax
A[Bleeed, 2] <= P[<pixel>](<op><ch value>);
# Add 52 to first two channels of pixel 12
A[Bleeed, 3] <= P[12](+52, +52);

# Set two pixels to 20
A[Bleeed, 4] <= P[3](20), P[4](20);</pre>
```



```
# Set function layer 2 pixels to white in 24-bit RGB
A[Bleeed, 5] <= PL[2](255,255,255);

# Function layer and pixel
A[Bleeed, 6] <= PL[2](300,200,100), P[30](30);

# Ranges and lists of pixels
A[Bleeed, 7] <= P[1-20](40);
A[Bleeed, 8] <= P[1,4,6,8,9](0x25);</pre>
```

8.2.1 Pixel Addressing

Pixels, as part of an animation, have a few different types of addressing. These make it easier to build animations more concisely and support a wide variety of keyboards with minimal/no modifications to the animation.

```
P[2]
             # Pixel index
            # Fill row
P[r:3]
P[c:10] # Fill column
P[r:3,c:10] # Rectangle index
P[r:5%,c:10%]
             # Rectangle % index
P[i+2]
             # Relative pixel index
P[r:i+3]
             # Relative row fill
P[c:i-10]
             # Relative column row fill
P[r:i-3,c:10] # Relative rectangle index
P[r: i+5\%, c: i-3\%]
             # Relative rectangle % index
U"A"
             # USB Code index (current layer)
S0x10
             # Scan Code index (current layer)
```

8.3 Triggers

Animations also generate a few different kinds of triggers. These triggers can be used for anything from starting another animation (i.e. linked animations), custom capabilties, or even USB keyboard output. The result syntax is identical to all other KLL triggers.

There are two types of triggers available: end and frame triggers. The



end trigger, triggers when the animation finishes all scheduled loops. This means that an infinitely running animation will never have an end trigger. Triggers do not go off if the animiation is forceably ended by means of an alternate trigger, but if another trigger sets an infinitely running animation to a finite number of loops, then it may trigger an end trigger. A frame trigger triggers whenever a certain frame is reached within an animation, regardless of how many loops the animation may be running for.

```
# End trigger
A[LongAnim] : <result>;

# Frame triggers
A[LongAnim, 3] : <result>;
A[ShortLED, 200] : <result>;
```

Per pixel triggers are not supported. However it is possible to extend the spec to support this if there are enough requests.

8.4 Results

Animations can also be dynamically controlled using a triggers. The standard results mechanism is used to interact with the animations.

All animation modifiers may be used to control the animation. See Section 8.2 for more details on each of the modifiers.

To be clear, it is completely valid to use an animation trigger to modify itself.

```
<trigger> : A[Dynamo];
<trigger> : A[Dynamo](frame:3, interp:on);
<trigger> : A[Dynamo](stop);
```

Pixels and pixel groups are limited to channel setting modifiers and perhaps any additional hardware modifiers that may be available.

```
# Operator on values to an 8-bit RGB pixel
<trigger> : P[23](+43,+21,-40);

# Set a pixel grouping layer 3 to 54
<trigger> : PL[3](54);
```



8.5 Pixel Positioning

In order to support complex animation support, each pixel can be assigned a physical position. This allows for turning sets of pixels into a display which can render basic fonts and images.

If the pixel was assigned to a Scan Code, then the pixel will inherit the positioning of the Scan Code key. However, you can still override the pixel position (will not affect the Scan Code position).

Each key may be assigned the following options, by default they are set to 0.

- x, y, z positions (mm)
- rx, ry, rz rotations (deg)

The units are in mm and degrees respectively.

```
# Set the x position 20 mm and x rotation 15 deg
P[30] <= x:20,rx:15;</pre>
```

Currently the size of the pixel is not taken into account. In general this should not matter for most purposes but it is possible to extend the spec to help deal with pixel shapes.

9 Compilation

Compilation is relatively simple. Reduce all triggers down to Scan Codes and all results into capabilities and USB Codes. To combine keymaps, they must be stacked during compilation. The first layout specified is the default. Each layout layered on top takes precedence over the layout underneath of it.

There is no requirement to support online key remapping, EEPROM storage or post compilation key remapping (pre microcontroller flashing).

Keys that are not mapped should be ignored and not present. Capabilities specified, but do not exist for a given keyboard are also ignored.

Warnings should be given about ambiguous ranges or no keymappings/trigger:result pairs are mapped.



Compilation should not succeed if there are missing mandatory variables or syntax problems. Additionally, there cannot be any duplicate capabilities defined, whether they are ignored or not.



10 USB Code Table

Following is a table of USB Codes. For each USB Code there is at least a long and short name. The names are case-insensitive. Some USB Codes have multiple names for convenience. Spaces and underscores both translate to underscore internally.

Please refer to the USB Keyboard HID spec for more details. All event based key codes that do not correspond to a physical key are not included in the table. For example, USB Code 0x01, which is a rollover error indicator.

Many USB Codes are recognized/implemented on the OS side. Do not expect lesser known USB Codes to "just work".

Table 10.1: Table of USB Codes

USB Code	Name	Alternate Name(s)
0x04 (4)	Α	
0x05 (5)	В	
0x06 (6)	C	
0x07 (7)	D	
0x08 (8)	E	
0x09 (9)	F	
0x0A (10)	G	
0x0B (11)	Н	
0x0C (12)	l I	
0x0D (13)	J	
0x0E (14)	K	
0x0F (15)	L	
0x10 (16)	M	
0x11 (17)	N	
0x12 (18)	0	
0x13 (19)	P	
0x14 (20)	Q	
0x15 (21)	R	
0x16 (22)	S	
0x17 (23)	Т	
0x18 (24)	U	
0x19 (25)	V	
0x1A (26)	W	
0x1B (27)	X	
0x1C (28)	Υ	



0x1D (29) 0x1E (30) 0x1F (31) 0x20 (32) 0x21 (33) 0x22 (34) 0x23 (35) 0x24 (36) 0x25 (37) 0x26 (38) 0x27 (39) 0x28 (40) 0x29 (41) 0x2A (42) 0x2B (43) 0x2C (44) 0x2D (45) 0x2E (46) 0x2F (47) 0x30 (48) 0x31 (49) 0x32 (50) 0x33 (51) 0x34 (52) 0x35 (53) 0x36 (54) 0x37 (55) 0x38 (56) 0x39 (57) 0x3A (58) 0x3B (59) 0x3C (60) 0x3D (61) 0x3E (62) 0x41 (65) 0x42 (66) 0x41 (65) 0x42 (66) 0x44 (68) 0x45 (69) 0x46 (70)	Z 1 2 3 4 5 6 7 8 9 0 Enter Esc Backspace Tab Space = [] , # ;; , / CapsLock F1 F2 F3 F4 F5 F6 F7 F8 F9 F10 F11 F12 PrintScreen	Minus Equals, Equal Left Bracket, LBracket Right Bracket, RBracket Backslash Number, Hash Semicolon Quote Backtick Comma Period Slash
---	---	---



0x47 (71) ScrollLock 0x48 (72) Pause 0x49 (73) Insert 0x4A (74) Home 0x4B (75) PageUp 0x4C (76) Delete 0x4D (77) End 0x4E (78) PageDown 0x4F (79) Right 0x50 (80) Left 0x51 (81) Down 0x52 (82) Up 0x53 (83) NumLock 0x54 (84) P/ Keypad Slash 0x55 (85) P* Keypad Asterisk 0x56 (86) P- Keypad Plus 0x57 (87) P+ Keypad Plus 0x58 (88) PEnter Keypad Enter 0x59 (89) P1 Keypad 1 0x58 (90) P2 Keypad 2 0x5B (91) P3 Keypad 3 0x5C (92) P4 Keypad 5 0x5E (94) P6 Keypad 6 0x5F (95) P7 Keypad 8 0x60 (96) P8 Keypad 9
0x49 (73) Insert 0x4A (74) Home 0x4B (75) PageUp 0x4C (76) Delete 0x4D (77) End 0x4E (78) PageDown 0x4F (79) Right 0x50 (80) Left 0x51 (81) Down 0x52 (82) Up 0x53 (83) NumLock 0x54 (84) P/ Keypad Slash 0x55 (85) P* Keypad Asterisk 0x56 (86) P- Keypad Plus 0x57 (87) P+ Keypad Plus 0x58 (88) PEnter Keypad Enter 0x59 (89) P1 Keypad 1 0x5A (90) P2 Keypad 2 0x5B (91) P3 Keypad 3 0x5C (92) P4 Keypad 4 0x5D (93) P5 Keypad 5 0x5E (94) P6 Keypad 7 0x60 (96) P8 Keypad 8
0x4A (74) Home 0x4B (75) PageUp 0x4C (76) Delete 0x4D (77) End 0x4E (78) PageDown 0x4F (79) Right 0x50 (80) Left 0x51 (81) Down 0x52 (82) Up 0x53 (83) NumLock 0x54 (84) P/ Keypad Slash 0x55 (85) P* Keypad Asterisk 0x56 (86) P- Keypad Plus 0x57 (87) P+ Keypad Plus 0x58 (88) PEnter Keypad Enter 0x59 (89) P1 Keypad 1 0x5A (90) P2 Keypad 2 0x5B (91) P3 Keypad 3 0x5C (92) P4 Keypad 4 0x5D (93) P5 Keypad 5 0x5E (94) P6 Keypad 7 0x60 (96) P8 Keypad 8
0x4B (75) PageUp 0x4C (76) Delete 0x4D (77) End 0x4E (78) PageDown 0x4F (79) Right 0x50 (80) Left 0x51 (81) Down 0x52 (82) Up 0x53 (83) NumLock 0x54 (84) P/ 0x55 (85) P* 0x56 (86) P- 0x57 (87) P+ 0x58 (88) PEnter 0x59 (89) P1 0x5A (90) P2 0x5B (91) P3 0x5D (92) P4 0x5D (93) P5 0x5E (94) P6 0x5F (95) P7 0x60 (96) P8 Keypad 8
0x4C (76) Delete 0x4D (77) End 0x4E (78) PageDown 0x4F (79) Right 0x50 (80) Left 0x51 (81) Down 0x52 (82) Up 0x53 (83) NumLock 0x54 (84) P/ Keypad Slash 0x55 (85) P* Keypad Asterisk 0x56 (86) P- Keypad Minus 0x57 (87) P+ Keypad Plus 0x58 (88) PEnter Keypad Enter 0x59 (89) P1 Keypad 1 0x5A (90) P2 Keypad 2 0x5B (91) P3 Keypad 3 0x5C (92) P4 Keypad 4 0x5D (93) P5 Keypad 5 0x5E (94) P6 Keypad 6 0x5F (95) P7 Keypad 8
0x4D (77) End 0x4E (78) PageDown 0x4F (79) Right 0x50 (80) Left 0x51 (81) Down 0x52 (82) Up 0x53 (83) NumLock 0x54 (84) P/ Keypad Slash 0x55 (85) P* Keypad Asterisk 0x56 (86) P- Keypad Plus 0x57 (87) P+ Keypad Plus 0x58 (88) PEnter Keypad Enter 0x59 (89) P1 Keypad 1 0x5A (90) P2 Keypad 2 0x5B (91) P3 Keypad 3 0x5C (92) P4 Keypad 4 0x5D (93) P5 Keypad 5 0x5E (94) P6 Keypad 7 0x5F (95) P7 Keypad 8
0x4E (78) PageDown 0x4F (79) Right 0x50 (80) Left 0x51 (81) Down 0x52 (82) Up 0x53 (83) NumLock 0x54 (84) P/ Keypad Slash 0x55 (85) P* Keypad Asterisk 0x56 (86) P- Keypad Plus 0x57 (87) P+ Keypad Plus 0x58 (88) PEnter Keypad Inter 0x59 (89) P1 Keypad 2 0x5A (90) P2 Keypad 3 0x5C (92) P4 Keypad 4 0x5D (93) P5 Keypad 5 0x5E (94) P6 Keypad 7 0x5F (95) P7 Keypad 8
0x4F (79) Right 0x50 (80) Left 0x51 (81) Down 0x52 (82) Up 0x53 (83) NumLock 0x54 (84) P/ Keypad Slash 0x55 (85) P* Keypad Asterisk 0x56 (86) P- Keypad Plus 0x57 (87) P+ Keypad Plus 0x58 (88) PEnter Keypad Enter 0x59 (89) P1 Keypad 1 0x5A (90) P2 Keypad 2 0x5B (91) P3 Keypad 3 0x5C (92) P4 Keypad 4 0x5D (93) P5 Keypad 5 0x5E (94) P6 Keypad 6 0x5F (95) P7 Keypad 7 0x60 (96) P8 Keypad 8
0x50 (80) Left 0x51 (81) Down 0x52 (82) Up 0x53 (83) NumLock 0x54 (84) P/ Keypad Slash 0x55 (85) P* Keypad Minus 0x56 (86) P- Keypad Plus 0x57 (87) P+ Keypad Plus 0x58 (88) PEnter Keypad Enter 0x59 (89) P1 Keypad 1 0x5A (90) P2 Keypad 2 0x5B (91) P3 Keypad 3 0x5C (92) P4 Keypad 4 0x5D (93) P5 Keypad 5 0x5E (94) P6 Keypad 6 0x5F (95) P7 Keypad 7 0x60 (96) P8 Keypad 8
0x51 (81) Down 0x52 (82) Up 0x53 (83) NumLock 0x54 (84) P/ Keypad Slash 0x55 (85) P* Keypad Minus 0x56 (86) P- Keypad Plus 0x57 (87) P+ Keypad Plus 0x58 (88) PEnter Keypad Enter 0x59 (89) P1 Keypad 1 0x5A (90) P2 Keypad 2 0x5B (91) P3 Keypad 3 0x5C (92) P4 Keypad 4 0x5D (93) P5 Keypad 5 0x5E (94) P6 Keypad 6 0x5F (95) P7 Keypad 7 0x60 (96) P8 Keypad 8
0x52 (82) Up 0x53 (83) NumLock 0x54 (84) P/ Keypad Slash 0x55 (85) P* Keypad Asterisk 0x56 (86) P- Keypad Minus 0x57 (87) P+ Keypad Plus 0x58 (88) PEnter Keypad Enter 0x59 (89) P1 Keypad 1 0x5A (90) P2 Keypad 2 0x5B (91) P3 Keypad 3 0x5C (92) P4 Keypad 4 0x5D (93) P5 Keypad 5 0x5E (94) P6 Keypad 6 0x5F (95) P7 Keypad 7 0x60 (96) P8 Keypad 8
0x53 (83) NumLock 0x54 (84) P/ Keypad Slash 0x55 (85) P* Keypad Asterisk 0x56 (86) P- Keypad Minus 0x57 (87) P+ Keypad Plus 0x58 (88) PEnter Keypad Enter 0x59 (89) P1 Keypad 1 0x5A (90) P2 Keypad 2 0x5B (91) P3 Keypad 3 0x5C (92) P4 Keypad 4 0x5D (93) P5 Keypad 5 0x5E (94) P6 Keypad 6 0x5F (95) P7 Keypad 7 0x60 (96) P8 Keypad 8
0x53 (83) NumLock 0x54 (84) P/ Keypad Slash 0x55 (85) P* Keypad Asterisk 0x56 (86) P- Keypad Minus 0x57 (87) P+ Keypad Plus 0x58 (88) PEnter Keypad Enter 0x59 (89) P1 Keypad 1 0x5A (90) P2 Keypad 2 0x5B (91) P3 Keypad 3 0x5C (92) P4 Keypad 4 0x5D (93) P5 Keypad 5 0x5E (94) P6 Keypad 6 0x5F (95) P7 Keypad 7 0x60 (96) P8 Keypad 8
0x54 (84) P/ Keypad Slash 0x55 (85) P* Keypad Asterisk 0x56 (86) P- Keypad Minus 0x57 (87) P+ Keypad Plus 0x58 (88) PEnter Keypad Enter 0x59 (89) P1 Keypad 1 0x5A (90) P2 Keypad 2 0x5B (91) P3 Keypad 3 0x5C (92) P4 Keypad 4 0x5D (93) P5 Keypad 5 0x5E (94) P6 Keypad 6 0x5F (95) P7 Keypad 7 0x60 (96) P8 Keypad 8
0x55 (85) P* Keypad Asterisk 0x56 (86) P- Keypad Minus 0x57 (87) P+ Keypad Plus 0x58 (88) PEnter Keypad Enter 0x59 (89) P1 Keypad 1 0x5A (90) P2 Keypad 2 0x5B (91) P3 Keypad 3 0x5C (92) P4 Keypad 4 0x5D (93) P5 Keypad 5 0x5E (94) P6 Keypad 6 0x5F (95) P7 Keypad 7 0x60 (96) P8 Keypad 8
0x57 (87) P+ Keypad Plus 0x58 (88) PEnter Keypad Enter 0x59 (89) P1 Keypad 1 0x5A (90) P2 Keypad 2 0x5B (91) P3 Keypad 3 0x5C (92) P4 Keypad 4 0x5D (93) P5 Keypad 5 0x5E (94) P6 Keypad 6 0x5F (95) P7 Keypad 7 0x60 (96) P8 Keypad 8
0x57 (87) P+ Keypad Plus 0x58 (88) PEnter Keypad Enter 0x59 (89) P1 Keypad 1 0x5A (90) P2 Keypad 2 0x5B (91) P3 Keypad 3 0x5C (92) P4 Keypad 4 0x5D (93) P5 Keypad 5 0x5E (94) P6 Keypad 6 0x5F (95) P7 Keypad 7 0x60 (96) P8 Keypad 8
0x58 (88) PEnter Keypad Enter 0x59 (89) P1 Keypad 1 0x5A (90) P2 Keypad 2 0x5B (91) P3 Keypad 3 0x5C (92) P4 Keypad 4 0x5D (93) P5 Keypad 5 0x5E (94) P6 Keypad 6 0x5F (95) P7 Keypad 7 0x60 (96) P8 Keypad 8
0x59 (89) P1 Keypad 1 0x5A (90) P2 Keypad 2 0x5B (91) P3 Keypad 3 0x5C (92) P4 Keypad 4 0x5D (93) P5 Keypad 5 0x5E (94) P6 Keypad 6 0x5F (95) P7 Keypad 7 0x60 (96) P8 Keypad 8
0x5A (90) P2 Keypad 2 0x5B (91) P3 Keypad 3 0x5C (92) P4 Keypad 4 0x5D (93) P5 Keypad 5 0x5E (94) P6 Keypad 6 0x5F (95) P7 Keypad 7 0x60 (96) P8 Keypad 8
0x5B (91) P3 Keypad 3 0x5C (92) P4 Keypad 4 0x5D (93) P5 Keypad 5 0x5E (94) P6 Keypad 6 0x5F (95) P7 Keypad 7 0x60 (96) P8 Keypad 8
0x5C (92) P4 Keypad 4 0x5D (93) P5 Keypad 5 0x5E (94) P6 Keypad 6 0x5F (95) P7 Keypad 7 0x60 (96) P8 Keypad 8
0x5D (93) P5 Keypad 5 0x5E (94) P6 Keypad 6 0x5F (95) P7 Keypad 7 0x60 (96) P8 Keypad 8
0x5E (94) P6 Keypad 6 0x5F (95) P7 Keypad 7 0x60 (96) P8 Keypad 8
0x5F (95) P7 Keypad 7 0x60 (96) P8 Keypad 8
0x60 (96) P8 Keypad 8
0x62 (98) P0 Keypad 0
0x63 (99) P. Keypad Decimal
0x64 (100) ISO/ ISO Slash
0x65 (101) App
0x67 (103) P= Keypad Equals
0x68 (104) F13
0x69 (105) F14
0x6A (106) F15
0x6B (107) F16
0x6C (108) F17
0x6D (109) F18
0x6E (110) F19
0x6F (111) F20
0x70 (112) F21
0x71 (113) F22



0x72 (114) F23 0x73 (115) F24 0x74 (116) Exec 0x75 (117) Help 0x76 (118) Menu 0x77 (119) Select 0x78 (120) Stop 0x78 (121) Again 0x7A (122) Undo 0x7B (123) Cut 0x7C (124) Copy 0x7D (125) Paste 0x7E (126) Find 0x7F (127) Mute 0x80 (128) VolumeDown 0x81 (129) VolumeDown 0x82 (130) CapsToggleLock 0x83 (131) NumToggleLock 0x84 (132) Reypad AS400 Equals 0x85 (133) P, 0x86 (134) Inter1 0x88 (136) Inter2 0x89 (137) Inter3 0x80 (140) Inter6 0x8B (139) Inter5 0x8E (142) Inter6 0x8E (142) Inter7 0x91 (144) Lang1 0x92 (146) Lan			
0x74 (116)	` '		
0x75 (117) Help 0x76 (118) Menu 0x77 (119) Select 0x78 (120) Stop 0x79 (121) Again 0x7A (122) Undo 0x7B (123) Cut 0x7C (124) Copy 0x7D (125) Paste 0x7E (126) Find 0x7F (127) Mute 0x80 (128) VolumeUp 0x81 (129) VolumeDown 0x82 (130) CapsToggleLock 0x83 (131) NumToggleLock 0x84 (132) ScrollToggleLock 0x85 (133) P, 0x86 (134) Keypad AS400 Equals 0x87 (135) Inter1 0x88 (136) Inter2 0x89 (137) Kanji (Kanji), Yen 0x80 (140) Inter3 0x8C (140) Inter4 0x8E (142) Inter5 0x8F (143) Inter6 0x9C (144) Lang1 0x91 (144) Lang2 0x92 (146) Lang3 0x93			
0x76 (118) Menu 0x77 (119) Select 0x78 (120) Stop 0x79 (121) Again 0x7A (122) Undo 0x7B (123) Cut 0x7C (124) Copy 0x7D (125) Paste 0x7F (127) Mute 0x80 (128) VolumeUp 0x81 (129) VolumeDown 0x82 (130) CapsToggleLock 0x84 (132) ScrollToggleLock 0x85 (133) P, 0x86 (134) Keypad AS400 Equals 0x87 (135) Inter1 0x88 (136) Inter2 0x89 (137) Inter3 0x80 (140) Inter3 0x8C (140) Inter5 0x8C (140) Inter6 0x8D (141) Inter7 0x8E (142) Inter8 0x9E (144) Lang1 0x90 (144) Lang1 0x91 (145) Lang2 0x92 (146) Lang3 0x95 (149) Lang4 0x96 (150)			
0x77 (119) Select 0x78 (120) Stop 0x79 (121) Again 0x7A (122) Undo 0x7B (123) Cut 0x7C (124) Copy 0x7D (125) Paste 0x7E (126) Find 0x7F (127) Mute 0x80 (128) VolumeUp 0x81 (129) VolumeDown 0x82 (130) CapsToggleLock 0x83 (131) NumToggleLock 0x85 (133) P, 0x86 (134) Keypad AS400 Equals 0x87 (135) Inter1 0x88 (136) Inter2 0x89 (137) Inter3 0x88 (138) Inter4 0x88 (139) Inter5 0x80 (140) Inter6 0x80 (141) Inter7 0x8E (142) Inter8 0x8F (143) Inter9 0x90 (144) Lang1 0x91 (145) Lang2 0x92 (146) Lang3 0x94 (148) Lang5 0x95 (149)		•	
0x78 (120) Stop 0x79 (121) Again 0x7A (122) Undo 0x7B (123) Cut 0x7C (124) Copy 0x7D (125) Paste 0x7F (127) Mute 0x80 (128) VolumeUp 0x81 (129) VolumeDown 0x82 (130) CapsToggleLock 0x83 (131) NumToggleLock 0x84 (132) ScrollToggleLock 0x85 (133) P, 0x86 (134) Keypad AS400 Equals 0x87 (135) Inter1 0x88 (136) Inter2 0x89 (137) Inter3 0x88 (138) Inter4 0x88 (139) Inter5 0x8B (139) Inter6 0x8C (140) Inter6 0x8E (142) Inter8 0x8F (143) Inter7 0x9G (144) Lang1 0x91 (144) Lang2 0x92 (146) Lang3 0x93 (147) Lang4 0x95 (149) Lang5 0x96 (150) <td>` ′ /</td> <td></td> <td></td>	` ′ /		
0x79 (121) Again 0x7A (122) Undo 0x7B (123) Cut 0x7C (124) Copy 0x7D (125) Paste 0x7F (126) Find 0x7F (127) Mute 0x80 (128) VolumeUp 0x81 (129) VolumeDown 0x82 (130) CapsToggleLock 0x83 (131) NumToggleLock 0x84 (132) ScrollToggleLock 0x85 (133) P, 0x86 (134) Keypad AS400 Equals 0x87 (135) Inter1 0x88 (136) Inter2 0x89 (137) Inter3 0x88 (138) Inter4 0x88 (139) Inter5 0x8B (139) Inter6 0x8C (140) Inter6 0x8E (142) Inter7 0x8E (142) Inter8 0x9C (144) Lang1 0x91 (145) Lang2 0x92 (146) Lang3 0x92 (148) Lang4 0x95 (149) Lang5 0x96 (150) <td></td> <td></td> <td></td>			
0x7A (122) Undo 0x7B (123) Cut 0x7C (124) Copy 0x7D (125) Paste 0x7F (127) Mute 0x80 (128) VolumeUp 0x81 (129) VolumeDown 0x82 (130) CapsToggleLock 0x83 (131) NumToggleLock 0x84 (132) ScrollToggleLock 0x85 (133) P, 0x86 (134) Keypad AS400 Equals 0x87 (135) Inter1 0x88 (136) Inter2 0x89 (137) Inter3 0x88 (139) Inter4 0x8B (139) Inter5 0x8C (140) Inter6 0x8D (141) Inter7 0x8E (142) Inter8 0x8F (143) Inter9 0x90 (144) Lang1 0x91 (145) Lang2 0x92 (146) Lang3 0x93 (147) Lang4 0x94 (148) Lang5 0x95 (149) Lang5 0x96 (150) Lang7 0x97 (151) </td <td></td> <td>•</td> <td></td>		•	
0x7B (123) Cut 0x7C (124) Copy 0x7D (125) Paste 0x7F (127) Mute 0x80 (128) VolumeUp 0x81 (129) VolumeDown 0x82 (130) CapsToggleLock 0x83 (131) NumToggleLock 0x84 (132) ScrollToggleLock 0x85 (133) P, 0x86 (134) Keypad AS400 Equals 0x87 (135) Inter1 0x88 (136) Inter2 0x89 (137) Inter3 0x88 (138) Inter4 0x88 (139) Inter5 0x8C (140) Inter6 0x8D (141) Inter6 0x8E (142) Inter8 0x8F (143) Inter9 0x90 (144) Lang1 0x91 (145) Lang2 0x92 (146) Lang3 0x93 (147) Lang4 0x94 (148) Lang5 0x95 (149) Lang6 0x96 (150) Lang7 0x97 (151) Lang8 0x98 (152)<			
0x7C (124) Copy 0x7D (125) Paste 0x7E (126) Find 0x7F (127) Mute 0x80 (128) VolumeUp 0x81 (129) VolumeDown 0x82 (130) CapsToggleLock 0x83 (131) NumToggleLock 0x84 (132) ScrollToggleLock 0x85 (133) P, 0x86 (134) Keypad AS400 Equals 0x87 (135) Inter1 0x88 (136) Inter2 0x88 (137) Inter3 0x88 (139) Inter4 0x8B (139) Inter5 0x8C (140) Inter5 0x8D (141) Inter6 0x8F (142) Inter8 0x8F (143) Inter9 0x90 (144) Lang1 0x91 (145) Lang2 0x92 (146) Lang3 0x93 (147) Lang4 0x94 (148) Lang5 0x96 (150) Lang7 0x97 (151) Lang8 0x98 (152) Lang9 0x99 (153)	, ,		
0x7D (125) Paste 0x7E (126) Find 0x7F (127) Mute 0x80 (128) VolumeUp 0x81 (129) VolumeDown 0x82 (130) CapsToggleLock 0x83 (131) NumToggleLock 0x84 (132) ScrollToggleLock 0x85 (133) P, 0x86 (134) Keypad AS400 Equals 0x87 (135) Inter1 0x88 (136) Inter2 0x89 (137) Inter3 0x88 (138) Inter4 0x88 (139) Inter5 0x8C (140) Inter6 0x8D (141) Inter7 0x8E (142) Inter8 0x8F (143) Inter9 0x90 (144) Lang1 0x91 (145) Lang2 0x92 (146) Lang3 0x93 (147) Lang4 0x94 (148) Lang5 0x96 (150) Lang7 0x97 (151) Lang8 0x98 (152) Lang9 0x99 (153) AltErase 0x9A (• •	Cut	
0x7E (126) Find 0x7F (127) Mute 0x80 (128) VolumeUp 0x81 (129) VolumeDown 0x82 (130) CapsToggleLock 0x83 (131) NumToggleLock 0x84 (132) ScrollToggleLock 0x85 (133) P, 0x86 (134) Keypad AS400 Equals 0x87 (135) Inter1 0x88 (136) Inter2 0x89 (137) Inter3 0x88 (138) Inter4 0x88 (139) Inter5 0x8C (140) Inter6 0x8D (141) Inter7 0x8E (142) Inter8 0x8F (143) Inter9 0x90 (144) Lang1 0x91 (145) Lang2 0x92 (146) Lang3 0x93 (147) Lang4 0x94 (148) Lang5 0x96 (150) Lang7 0x97 (151) Lang8 0x98 (152) Lang9 0x99 (153) AltErase 0x9A (154) SysReq	0x7C (124)	Сору	
0x7F (127) Mute 0x80 (128) VolumeUp 0x81 (129) VolumeDown 0x82 (130) CapsToggleLock 0x83 (131) NumToggleLock 0x84 (132) ScrollToggleLock 0x85 (133) P, 0x86 (134) Keypad AS400 Equals 0x87 (135) Inter1 0x88 (136) Inter2 0x89 (137) Inter3 0x84 (138) Inter4 0x88 (139) Inter5 0x8C (140) Inter6 0x8D (141) Inter7 0x8E (142) Inter8 0x8F (143) Inter9 0x90 (144) Lang1 0x91 (145) Lang2 0x92 (146) Lang3 0x93 (147) Lang4 0x94 (148) Lang5 0x96 (150) Lang7 0x97 (151) Lang8 0x98 (152) Lang9 0x99 (153) AltErase 0x9A (154) SysReq	0x7D (125)	Paste	
0x80 (128) VolumeUp 0x81 (129) VolumeDown 0x82 (130) CapsToggleLock 0x83 (131) NumToggleLock 0x84 (132) ScrollToggleLock 0x85 (133) P, 0x86 (134) Keypad AS400 Equals 0x87 (135) Inter1 0x88 (136) Inter2 0x89 (137) Inter3 0x89 (137) Inter3 0x88 (138) Inter4 0x88 (139) Inter5 0x8C (140) Inter6 0x8C (140) Inter6 0x8E (142) Inter8 0x8F (143) Inter9 0x90 (144) Lang1 0x91 (145) Lang2 0x92 (146) Lang3 0x93 (147) Lang4 0x94 (148) Lang5 0x96 (150) Lang7 0x97 (151) Lang8 0x98 (152) Lang9 0x99 (153) AltErase 0x9A (154) SysReq	0x7E (126)	Find	
0x81 (129) VolumeDown 0x82 (130) CapsToggleLock 0x83 (131) NumToggleLock 0x84 (132) ScrollToggleLock 0x85 (133) P, 0x86 (134) Keypad AS400 Equals 0x87 (135) Inter1 0x88 (136) Inter2 0x89 (137) Inter3 0x89 (137) Inter3 0x84 (138) Inter4 0x88 (139) Inter5 0x8C (140) Inter6 0x8D (141) Inter6 0x8E (142) Inter8 0x8F (143) Inter9 0x90 (144) Lang1 0x91 (145) Lang2 0x92 (146) Lang3 0x93 (147) Lang4 0x94 (148) Lang5 0x96 (150) Lang7 0x97 (151) Lang8 0x98 (152) Lang9 0x99 (153) AltErase 0x9A (154) SysReq	0x7F (127)	Mute	
0x82 (130) CapsToggleLock 0x83 (131) NumToggleLock 0x84 (132) ScrollToggleLock 0x85 (133) P, 0x86 (134) Keypad AS400 Equals 0x87 (135) Inter1 0x88 (136) Inter2 0x89 (137) Inter3 0x84 (138) Inter4 0x88 (139) Inter5 0x8C (140) Inter6 0x8D (141) Inter7 0x8E (142) Inter8 0x8F (143) Inter9 0x90 (144) Lang1 0x91 (145) Lang2 0x92 (146) Lang3 0x93 (147) Lang4 0x94 (148) Lang5 0x96 (150) Lang6 0x97 (151) Lang8 0x98 (152) Lang9 0x99 (153) AltErase 0x9A (154) SysReq	0x80 (128)	VolumeUp	
0x83 (131) NumToggleLock 0x84 (132) ScrollToggleLock 0x85 (133) P, 0x86 (134) Keypad AS400 Equals 0x87 (135) Inter1 0x88 (136) Inter2 0x89 (137) Inter3 0x84 (138) Inter4 0x88 (139) Inter5 0x80 (140) Inter6 0x8D (141) Inter7 0x8E (142) Inter8 0x8F (143) Inter9 0x90 (144) Lang1 0x91 (145) Lang2 0x92 (146) Lang3 0x93 (147) Lang4 0x94 (148) Lang5 0x95 (149) Lang6 0x97 (151) Lang8 0x98 (152) Lang9 0x99 (153) AltErase 0x9A (154) SysReq	0x81 (129)	VolumeDown	
0x84 (132) ScrollToggleLock Keypad Comma 0x85 (133) P, Keypad AS400 Equals 0x87 (135) Inter1 Kanji1 0x88 (136) Inter2 Kanji2, Kana 0x89 (137) Inter3 Kanji3, Yen 0x8A (138) Inter4 Kanji4, Henkan 0x8B (139) Inter5 Kanji6, Muhenkan 0x8C (140) Inter6 Kanji6, Kanji7, ByteToggle 0x8D (141) Inter7 Kanji8 0x8E (142) Inter8 Kanji9 0x8F (143) Inter9 Kanji9 0x90 (144) Lang1 HangulEnglish 0x91 (145) Lang2 Hanja, Eisu 0x92 (146) Lang3 Katakana 0x93 (147) Lang4 Hiragana 0x94 (148) Lang5 ZenkakuHankaku 0x95 (149) Lang6 0x97 (151) Lang8 0x98 (152) AltErase 0x9A (154) SysReq	0x82 (130)	CapsToggleLock	
0x85 (133) P, Keypad Comma 0x86 (134) Keypad AS400 Equals 0x87 (135) Inter1 0x88 (136) Inter2 0x89 (137) Inter3 0x8A (138) Inter4 0x8B (139) Inter5 0x8C (140) Inter6 0x8D (141) Inter7 0x8E (142) Inter8 0x8F (143) Inter9 0x90 (144) Lang1 0x91 (145) Lang2 0x92 (146) Lang3 0x93 (147) Lang4 0x94 (148) Lang5 0x96 (150) Lang6 0x97 (151) Lang8 0x98 (152) Lang9 0x99 (153) AltErase 0x9A (154) SysReq	0x83 (131)	NumToggleLock	
0x86 (134) Keypad AS400 Equals 0x87 (135) Inter1 Kanji1 0x88 (136) Inter2 Kanji2, Kana 0x89 (137) Inter3 Kanji3, Yen 0x8A (138) Inter4 Kanji4, Henkan 0x8B (139) Inter5 Kanji5, Muhenkan 0x8C (140) Inter6 Kanji6 0x8D (141) Inter7 Kanji7, ByteToggle 0x8E (142) Inter8 Kanji8 0x8F (143) Inter9 Kanji9 0x90 (144) Lang1 HangulEnglish 0x91 (145) Lang2 Hanja, Eisu 0x92 (146) Lang3 Katakana 0x93 (147) Lang4 Hiragana 0x94 (148) Lang5 ZenkakuHankaku 0x95 (149) Lang6 0x97 (151) Lang8 0x98 (152) Lang9 0x99 (153) AltErase 0x9A (154) SysReq	0x84 (132)	ScrollToggleLock	
0x87 (135) Inter1 Kanji1 0x88 (136) Inter2 Kanji2, Kana 0x89 (137) Inter3 Kanji3, Yen 0x8A (138) Inter4 Kanji4, Henkan 0x8B (139) Inter5 Kanji5, Muhenkan 0x8C (140) Inter6 Kanji6 0x8D (141) Inter7 Kanji7, ByteToggle 0x8E (142) Inter8 Kanji8 0x8F (143) Inter9 Kanji9 0x90 (144) Lang1 HangulEnglish 0x91 (145) Lang2 Hanja, Eisu 0x92 (146) Lang3 Katakana 0x93 (147) Lang4 Hiragana 0x94 (148) Lang5 ZenkakuHankaku 0x95 (149) Lang6 Lang7 0x96 (150) Lang7 Lang8 0x98 (152) Lang9 0x99 (153) AltErase 0x9A (154) SysReq	0x85 (133)	P,	Keypad Comma
0x88 (136) Inter2 Kanji2, Kana 0x89 (137) Inter3 Kanji3, Yen 0x8A (138) Inter4 Kanji4, Henkan 0x8B (139) Inter5 Kanji5, Muhenkan 0x8C (140) Inter6 Kanji6 0x8D (141) Inter7 Kanji7, ByteToggle 0x8E (142) Inter8 Kanji8 0x8F (143) Inter9 Kanji9 0x90 (144) Lang1 HangulEnglish 0x91 (145) Lang2 Hanja, Eisu 0x92 (146) Lang3 Katakana 0x93 (147) Lang4 Hiragana 0x94 (148) Lang5 ZenkakuHankaku 0x95 (149) Lang6 0x96 (150) Lang7 0x97 (151) Lang8 0x98 (152) Lang9 0x99 (153) AltErase 0x9A (154) SysReq	0x86 (134)	Keypad AS400 Equals	
0x89 (137) Inter3 Kanji3, Yen 0x8A (138) Inter4 Kanji4, Henkan 0x8B (139) Inter5 Kanji5, Muhenkan 0x8C (140) Inter6 Kanji6 0x8D (141) Inter7 Kanji7, ByteToggle 0x8E (142) Inter8 Kanji8 0x8F (143) Inter9 Kanji9 0x90 (144) Lang1 HangulEnglish 0x91 (145) Lang2 Hanja, Eisu 0x92 (146) Lang3 Katakana 0x93 (147) Lang4 Hiragana 0x94 (148) Lang5 ZenkakuHankaku 0x95 (149) Lang6 Lang7 0x96 (150) Lang8 Lang9 0x98 (152) Lang9 0x99 (153) AltErase 0x9A (154) SysReq	0x87 (135)	Inter1	Kanji1
0x8A (138) Inter4 Kanji4, Henkan 0x8B (139) Inter5 Kanji5, Muhenkan 0x8C (140) Inter6 Kanji6 0x8D (141) Inter7 Kanji7, ByteToggle 0x8E (142) Inter8 Kanji8 0x8F (143) Inter9 Kanji9 0x90 (144) Lang1 HangulEnglish 0x91 (145) Lang2 Hanja, Eisu 0x92 (146) Lang3 Katakana 0x93 (147) Lang4 Hiragana 0x94 (148) Lang5 ZenkakuHankaku 0x95 (149) Lang6 Lang7 0x96 (150) Lang8 Lang9 0x98 (152) Lang9 0x99 (153) AltErase 0x9A (154) SysReq	0x88 (136)	Inter2	Kanji2, Kana
0x8B (139) Inter5 Kanji5, Muhenkan 0x8C (140) Inter6 Kanji6 0x8D (141) Inter7 Kanji7, ByteToggle 0x8E (142) Inter8 Kanji8 0x8F (143) Inter9 Kanji9 0x90 (144) Lang1 HangulEnglish 0x91 (145) Lang2 Katakana 0x92 (146) Lang3 Katakana 0x93 (147) Lang4 Hiragana 0x94 (148) Lang5 ZenkakuHankaku 0x95 (149) Lang6 0x96 (150) Lang7 0x97 (151) Lang8 0x98 (152) Lang9 0x99 (153) AltErase 0x9A (154) SysReq	0x89 (137)	Inter3	Kanji3, Yen
0x8C (140) Inter6 Kanji6 0x8D (141) Inter7 Kanji7, ByteToggle 0x8E (142) Inter8 Kanji8 0x8F (143) Inter9 Kanji9 0x90 (144) Lang1 HangulEnglish 0x91 (145) Lang2 Katakana 0x92 (146) Lang3 Katakana 0x93 (147) Lang4 Hiragana 0x94 (148) Lang5 ZenkakuHankaku 0x95 (149) Lang6 0x96 (150) Lang7 0x97 (151) Lang8 0x98 (152) Lang9 0x99 (153) AltErase 0x9A (154) SysReq	0x8A (138)	Inter4	Kanji4, Henkan
0x8D (141) Inter7 Kanji7, ByteToggle 0x8E (142) Inter8 Kanji8 0x8F (143) Inter9 Kanji9 0x90 (144) Lang1 HangulEnglish 0x91 (145) Lang2 Hanja, Eisu 0x92 (146) Lang3 Katakana 0x93 (147) Lang4 Hiragana 0x94 (148) Lang5 ZenkakuHankaku 0x95 (149) Lang6 Lang7 0x96 (150) Lang8 Lang9 0x98 (152) Lang9 AltErase 0x9A (154) SysReq	0x8B (139)	Inter5	Kanji5, Muhenkan
0x8E (142) Inter8 Kanji8 0x8F (143) Inter9 Kanji9 0x90 (144) Lang1 HangulEnglish 0x91 (145) Lang2 Hanja, Eisu 0x92 (146) Lang3 Katakana 0x93 (147) Lang4 Hiragana 0x94 (148) Lang5 ZenkakuHankaku 0x95 (149) Lang6 Lang7 0x96 (150) Lang8 Lang8 0x98 (152) Lang9 AltErase 0x9A (154) SysReq	0x8C (140)	Inter6	_
0x8F (143) Inter9 Kanji9 0x90 (144) Lang1 HangulEnglish 0x91 (145) Lang2 Hanja, Eisu 0x92 (146) Lang3 Katakana 0x93 (147) Lang4 Hiragana 0x94 (148) Lang5 ZenkakuHankaku 0x95 (149) Lang6 0x96 (150) Lang7 0x97 (151) Lang8 0x98 (152) Lang9 0x99 (153) AltErase 0x9A (154) SysReq	0x8D (141)	Inter7	
0x90 (144) Lang1 HangulEnglish 0x91 (145) Lang2 Hanja, Eisu 0x92 (146) Lang3 Katakana 0x93 (147) Lang4 Hiragana 0x94 (148) Lang5 ZenkakuHankaku 0x95 (149) Lang6 Lang7 0x96 (150) Lang8 Lang8 0x98 (152) Lang9 AltErase 0x9A (154) SysReq	0x8E (142)	Inter8	Kanji8
0x91 (145) Lang2 Hanja, Eisu 0x92 (146) Lang3 Katakana 0x93 (147) Lang4 Hiragana 0x94 (148) Lang5 ZenkakuHankaku 0x95 (149) Lang6 0x96 (150) Lang7 0x97 (151) Lang8 0x98 (152) Lang9 0x99 (153) AltErase 0x9A (154) SysReq	0x8F (143)	Inter9	_
0x92 (146) Lang3 Katakana 0x93 (147) Lang4 Hiragana 0x94 (148) Lang5 ZenkakuHankaku 0x95 (149) Lang6 0x96 (150) Lang7 0x97 (151) Lang8 0x98 (152) Lang9 0x99 (153) AltErase 0x9A (154) SysReq	0x90 (144)	Lang1	
0x93 (147) Lang4 Hiragana 0x94 (148) Lang5 ZenkakuHankaku 0x95 (149) Lang6 0x96 (150) Lang7 0x97 (151) Lang8 0x98 (152) Lang9 0x99 (153) AltErase 0x9A (154) SysReq	0x91 (145)	Lang2	Hanja, Eisu
0x94 (148) Lang5 ZenkakuHankaku 0x95 (149) Lang6 0x96 (150) Lang7 0x97 (151) Lang8 0x98 (152) Lang9 0x99 (153) AltErase 0x9A (154) SysReq	0x92 (146)	Lang3	Katakana
0x95 (149) Lang6 0x96 (150) Lang7 0x97 (151) Lang8 0x98 (152) Lang9 0x99 (153) AltErase 0x9A (154) SysReq	0x93 (147)	Lang4	
0x96 (150) Lang7 0x97 (151) Lang8 0x98 (152) Lang9 0x99 (153) AltErase 0x9A (154) SysReq	0x94 (148)	Lang5	ZenkakuHankaku
0x97 (151) Lang8 0x98 (152) Lang9 0x99 (153) AltErase 0x9A (154) SysReq	0x95 (149)		
0x98 (152) Lang9 0x99 (153) AltErase 0x9A (154) SysReq	0x96 (150)		
0x99 (153) AltErase 0x9A (154) SysReq	0x97 (151)	Lang8	
0x9A (154) SysReq	0x98 (152)	Lang9	
	-	AltErase	
0x9B (155) Cancel	0x9A (154)	SysReq	
	0x9B (155)	Cancel	



0x9C (156)	Clear	
0x9D (157)	Prior	
0x9E (158)	Return	
0x9F (159)	Sep	Separator
0xA0 (160)	Out	
0xA1 (161)	Oper	
0xA2 (162)	Clear	
0xA3 (163)	CrSel	
0xA4 (164)	ExSel	
0xB0 (176)	P00	Keypad 00
0xB1 (177)	P000	Keypad 000
0xB2 (178)	1000Sep	ThousandSeparator
0xB3 (179)	DecimalSep	DecimalSeparator
0xB4 (180)	Currency	CurrencyUnit
0xB5 (181)	CurrencySub	CurrencySubUnit
0xB6 (182)	P(Keypad Left Parentheses
0xB7 (183)	P)	Keypad Right Parentheses
0xB8 (184)	P{	Keypad Left Brace
0xB9 (185)	P}	Keypad Right Brace
0xBA (186)	PTab	Keypad Tab
0xBB (187)	PBackspace	Keypad Backspace
0xBC (188)	PA	Keypad A
0xBD (189)	PB	Keypad B
0xBE (190)	PC	Keypad C
0xBF (191)	PD	Keypad D
0xC0 (192)	PE	Keypad E
0xC1 (193)	PF	Keypad F
0xC2 (194)	PXOR	Keypad XOR
0xC3 (195)	P^	Keypad Chevron
0xC4 (196)	P%	Keypad Percent
0xC5 (197)	P<	Keypad LessThan
0xC6 (198)	P>	Keypad GreaterThan
0xC7 (199)	P&	Keypad BitAnd
0xC8 (200)	P&&	Keypad And
0xC9 (201)	PI	Keypad BitOr
0xCA (202)	PII	Keypad Or
0xCB (203)	P:	Keypad Colon
0xCC (204)	P#	Keypad Number, Keypad Hash
0xCD (205)	PSpace	Keypad Space
0xCE (206)	P@	Keypad At
0xCF (207)	P!	Keypad Exclaim
0xD0 (208)	PMemStore	Keypad MemStore
	ı	ı



0xD1 (209) 0xD2 (210) 0xD3 (211) 0xD4 (212) 0xD5 (213) 0xD6 (214) 0xD7 (215) 0xD8 (216)	PMemRecall PMemClear PMemAdd PMemSub PMemMult PMemDiv P+/- PClear	Keypad MemRecall Keypad MemClear Keypad MemAdd Keypad MemSub Keypad MemMult Keypad MemDiv Keypad PlusMinus Keypad Clear
0xD9 (217) 0xDA (218)	PClearEntry PBinary	Keypad ClearEntry Keypad Binary
0xDB (219) 0xDC (220) 0xDD (221)	POctal PDecimal PHex	Keypad Octal Keypad Decimal Keypad Hex
0xE0 (224)	LCtrl	Left Ctrl, Ctrl
0xE1 (225)	LShift	Left Shift, Shift
0xE2 (226)	LAIt	Left Alt, Alt
0xE3 (227)	LGui	Left Gui, Gui
0xE4 (228)	RCtrl	Right Ctrl
0xE5 (229)	RShift	Right Shift
0xE6 (230)	RAIt	Right Alt
0xE7 (231)	RGui	Right Gui
0xF0 (240)	Function1	Fun1, Fun
0xF1 (241)	Function2	Fun2
0xF2 (242)	Function3	Fun3
0xF3 (243)	Function4	Fun4
0xF4 (244)	Function5	Fun5
0xF5 (245)	Function6	Fun6
0xF6 (246)	Function7	Fun7
0xF7 (247)	Function8	Fun8
0xF8 (248)	Function9	Fun9
0xF9 (249)	Function10	Fun10
0xFA (250)	Function11	Fun11
0xFB (251)	Function12	Fun12
0xFC (252)	Function13	Fun13
0xFD (253)	Function14	Fun14
0xFE (254)	Function15	Fun16
0xFF (255)	Function16	Fun16
0x100 (256)	Lock1	Lck1, Lck Lck2
0x101 (257)	Lock2	
0x102 (258) 0x103 (259)	Lock3 Lock4	Lck3 Lck4
0x103 (259) 0x104 (260)	Lock4 Lock5	Lck4 Lck5
UXIU4 (200)	LUCKS	LCNJ



0x105 (261)	Lock6	Lck6
0x106 (262)	Lock7	Lck7
0x107 (263)	Lock8	Lck8
0x108 (264)	Lock9	Lck9
0x109 (265)	Lock10	Lck10
0x10A (266)	Lock11	Lck11
0x10B (267)	Lock12	Lck12
0x10C (268)	Lock13	Lck13
0x10D (269)	Lock14	Lck14
0x10E (270)	Lock15	Lck15
0x10F (271)	Lock16	Lck16
0x110 (272)	Latch1	Lat1, Lat
0x111 (273)	Latch2	Lat2
0x112 (274)	Latch3	Lat3
0x113 (275)	Latch4	Lat4
0x114 (276)	Latch5	Lat5
0x115 (277)	Latch6	Lat6
0x116 (278)	Latch7	Lat7
0x117 (279)	Latch8	Lat8
0x118 (280)	Latch9	Lat9
0x119 (281)	Latch10	Lat10
0x11A (282)	Latch11	Lat11
0x11B (283)	Latch12	Lat12
0x11C (284)	Latch13	Lat13
0x11D (285)	Latch14	Lat14
0x11E (286)	Latch15	Lat15
0x11F (287)	Latch16	Lat16
0x120 (288)	Next Layer	NLayer
0x121 (289)	Prev Layer	PLayer

As function keys are not part of the USB HID spec, they are difficult to reference using USB Codes. To get around this, KLL reserves USB Codes 0xF0 to 0xFF for function keys. It is possible (though unlikely) that a new USB HID spec may use this reserved space. In that case, a new revision of KLL will be made to address this issue. USB Codes 0xF0 to 0xFF are never sent via USB and are for internal processing only.

It is possible to use any arbitrary USB Code as a function key. However, using something like a SysReq as your function key (in the default map) makes it unclear to other readers unless you explicitly comment this case in the .kll file.



11 System Control Code Table

Following is a table of USB System Control Codes. These are useful for defining keys to signal the OS to power off, sleep or eject something.

Please refer to the USB HID spec for more details. Do not expect your OS to recognize these codes. Many of them are system specific.

Table 11.1: Table of System Control Codes

Sys Code	Name	Alternate Name(s)
0x81	PowerDown	
0x82	Sleep	
0x83	WakeUp	
0x84	ContextMenu	
0x85	MainMenu	
0x86	AppMenu	
0x87	MenuHelp	
0x88	MenuExit	
0x89	MenuSelect	
A8x0	MenuRight	
0x8B	MenuLeft	
0x8C	MenuUp	
0x8D	MenuDown	
0x8E	ColdRestart	
0x8F	WarmRestart	
0x90	DpadUp	
0x91	DpadDown	
0x92	DpadRight	
0x93	DpadLeft	
0xA0	Dock	
0xA1	Undock	
0xA2	Setup	
0xA3	Break	
0xA4	DebuggerBreak	
0xA5	AppBreak	
0xA6	AppDebuggerBreak	
0xA7	SpeakerMute	
0xA8	Hibernate	
0xB0	DispInvert	
0xB1	DispInternal	
0xB2	DispExternal	



0xB3	DispBoth
0xB4	DispDual
0xB5	DispToggleIntExt
0xB6	DispSwapPriSec
0xB7	DispLcdAutoscale



12 Consumer Control Code Table

Following is a table of USB Consumer Control Codes. These are useful for defining media keys such as Next, Previous, Pause, etc.

Please refer to the USB HID spec for more details. Do not expect your OS to recognize these codes. Many of them are system specific.

Table 12.1: Table of Consumer Control Codes

Cons Code	Name	Alternate Name(s)
0x020	10	
0x021	100	
0x022	AmPm	
0x030	Power	
0x031	Reset	
0x032	Sleep	
0x033	SleepAfter	
0x034	SleepMode	
0x035	Illumination	
0x040	Menu	
0x041	MenuPick	
0x042	MenuUp	
0x043	MenuDown	
0x044	MenuLeft	
0x045	MenuRight	
0x046	MenuEscape	
0x047	MenuValueIncrease	
0x048	MenuValueDecrease	
0x060	DataOnScreen	
0x061	ClosedCaption	
0x062	ClosedCaptionSelect	
0x063	VcrTv	
0x064	BroadcastMode	
0x065	Snapshot	
0x066	Still	
0x06F	BrightnessIncrement	
0x070	BrightnessDecrement	
0x072	BacklightToggle	
0x073	BrightnessMin	
0x074	BrightnessMax	



0x081 AssignSelection 0x082 ModeStep 0x083 RecallLast 0x084 EnterChannel 0x085 OrderMovie 0x088 MediaComputer 0x089 MediaTv 0x080 MediaTwww 0x080 MediaDvd 0x081 MediaDvd 0x082 MediaProgramGuide 0x084 MediaVideoPhone 0x085 MediaSelectGames 0x090 MediaSelectMessages 0x091 MediaSelectTwessages 0x092 MediaSelectTuner 0x093 MediaSelectTuner 0x094 Quit 0x095 Help 0x096 MediaSelectTape 0x097 MediaSelectCall 0x098 MediaSelectLecurity 0x099 MediaSelectCall 0x090 MediaSelectSecurity 0x091 MediaSelectSecurity 0x092 MediaSelectSap 0x093 MediaSelectSap 0x094 MediaSelectSap	0x075	BrightnessAuto	
0x083 RecallLast 0x084 EnterChannel 0x088 MediaComputer 0x089 MediaTV 0x08A MediaWww 0x08B MediaDvd 0x08C MediaTelephone 0x08D MediaProgramGuide 0x08E MediaVideoPhone 0x08F MediaSelectGames 0x090 MediaSelectTGames 0x091 MediaSelectTMessages 0x091 MediaSelectTuner 0x092 MediaSelectTuner 0x093 MediaSelectTuner 0x094 Quit 0x095 Help 0x096 MediaSelectTape 0x097 MediaSelectSatellite 0x098 MediaSelectSecurity 0x09A MediaSelectHome 0x09B MediaSelectHome 0x09C Channellncrement 0x09D CahnnelDecrement 0x09E MediaSelectSap 0x0A0 VcrPlus 0x0A1 Once 0x0A2 Daily <	0x081	AssignSelection	
0x084 EnterChannel 0x085 OrderMovie 0x088 MediaComputer 0x089 MediaTv 0x08A MediaWww 0x08B MediaDvd 0x08C MediaTelephone 0x08D MediaProgramGuide 0x08E MediaVideoPhone 0x08E MediaSelectCames 0x090 MediaSelectMessages 0x091 MediaSelectTode 0x092 MediaSelectTuner 0x093 MediaSelectTuner 0x094 Quit 0x095 Help 0x096 MediaSelectTape 0x097 MediaSelectCable 0x098 MediaSelectHome 0x099 MediaSelectCall 0x09A MediaSelectCall 0x09B MediaSelectCall 0x09C ChannelIncrement 0x09D CahnnelIncrement 0x09E MediaSelectSap 0x0A1 Once 0x0A2 Daily 0x0A3 Weekly <	0x082	ModeStep	
0x085OrderMovie0x088MediaComputer0x089MediaTv0x08AMediaTv0x08BMediaDvd0x08CMediaTelephone0x08DMediaProgramGuide0x08EMediaSelectGames0x090MediaSelectMessages0x091MediaSelectMessages0x092MediaSelectTuner0x093MediaSelectTuner0x094Quit0x095Help0x096MediaSelectCable0x097MediaSelectSatellite0x098MediaSelectSecurity0x09AMediaSelectSecurity0x09BMediaSelectCall0x09CChannelIncrement0x09DCahnnelDecrement0x09EMediaSelectSap0x0A0VcrPlus0x0A1Once0x0A2Daily0x0A3Weekly0x0A4Monthly0x0B0Play0x0B1Pause0x0B2Record0x0B3FastForward0x0B4Rewind0x0B5ScanNextTrack0x0B6ScanPreviousTrack	0x083	RecallLast	
0x088MediaComputer0x089MediaTv0x08AMediaWww0x08BMediaDvd0x08CMediaTelephone0x08DMediaProgramGuide0x08EMediaSelectGames0x090MediaSelecttGames0x091MediaSelectVcr0x092MediaSelectTuner0x094Quit0x095MediaSelectTape0x096MediaSelectTape0x097MediaSelectSatellite0x099MediaSelectSecurity0x09AMediaSelectHome0x09BMediaSelectHome0x09CChannelIncrement0x09DCahnnelDecrement0x09EMediaSelectSap0x0A0VcrPlus0x0A1Once0x0A2Daily0x0A3Weekly0x0A4Monthly0x0B0Play0x0B1Pause0x0B2Record0x0B3FastForward0x0B4Rewind0x0B5ScanNextTrack0x0B6ScanPreviousTrack	0x084	EnterChannel	
0x089 MediaTv 0x08A MediaWww 0x08B MediaDvd 0x08C MediaTelephone 0x08D MediaProgramGuide 0x08E MediaSelectGames 0x090 MediaSelectCd 0x091 MediaSelectVcr 0x093 MediaSelectTuner 0x094 Quit 0x095 Help 0x096 MediaSelectCable 0x098 MediaSelectSatellite 0x099 MediaSelectSecurity 0x098 MediaSelectSecurity 0x099 MediaSelectSecurity 0x09A MediaSelectCall 0x09C ChannelIncrement 0x09B MediaSelectSap 0x0A0 VcrPlus 0x0A0 VcrPlus 0x0A1 Once 0x0A2 Daily 0x0A3 Weekly 0x0A4 Monthly 0x0B0 Play 0x0B1 Pause 0x0B2 Record 0x0B3 FastForward 0x0B4 Rewind 0x0B5 ScanNextTrack 0x0B5 ScanPreviousTrack	0x085	OrderMovie	
0x08AMediaDww0x08BMediaTelephone0x08CMediaProgramGuide0x08BMediaVideoPhone0x08FMediaSelectGames0x090MediaSelectMessages0x091MediaSelectCd0x092MediaSelectTuner0x093MediaSelectTuner0x094Quit0x095Help0x096MediaSelectTape0x097MediaSelectSatellite0x098MediaSelectSecurity0x090MediaSelectHome0x09BMediaSelectCall0x09CChannelIncrement0x09DCahnnelDecrement0x09EMediaSelectSap0x0A0VcrPlus0x0A1Once0x0A2Daily0x0A3Weekly0x0A4Monthly0x0B0Play0x0B1Pause0x0B2Record0x0B3FastForward0x0B4Rewind0x0B5ScanNextTrack0x0B6ScanPreviousTrack	0x088	MediaComputer	
0x08B MediaTelephone 0x08C MediaTelephone 0x08D MediaProgramGuide 0x08E MediaSelectGames 0x090 MediaSelectMessages 0x091 MediaSelectCd 0x092 MediaSelectTuner 0x093 MediaSelectTuner 0x094 Quit 0x095 Help 0x096 MediaSelectTape 0x097 MediaSelectSeurity 0x098 MediaSelectSecurity 0x099 MediaSelectHome 0x099 MediaSelectCall 0x090 ChannelIncrement 0x091 CahnnelDecrement 0x092 Once 0x040 VcrPlus 0x0A0 VcrPlus 0x0A1 Once 0x0A2 Daily 0x0A3 Weekly 0x0A4 Monthly 0x0B0 Play 0x0B1 Pause 0x0B2 Record 0x0B3 FastForward 0x0B4 Rewind<	0x089	MediaTv	
0x08C MediaTelephone 0x08D MediaProgramGuide 0x08E MediaVideoPhone 0x08F MediaSelectGames 0x090 MediaSelectCd 0x091 MediaSelectCd 0x092 MediaSelectVcr 0x093 MediaSelectTuner 0x094 Quit 0x095 Help 0x096 MediaSelectTape 0x097 MediaSelectCable 0x098 MediaSelectSecurity 0x099 MediaSelectSecurity 0x09A MediaSelectHome 0x09B MediaSelectCall 0x09C ChannelIncrement 0x09E MediaSelectSap 0x0A0 VcrPlus 0x0A0 Once 0x0A1 Once 0x0A2 Daily 0x0A3 Weekly 0x0A4 Monthly 0x0B0 Play 0x0B1 Pause 0x0B2 Record 0x0B3 FastForward 0x0B4 Rewind	0x08A	MediaWww	
0x08DMediaProgramGuide0x08EMediaVideoPhone0x08FMediaSelectGames0x090MediaSelectMessages0x091MediaSelectVcr0x092MediaSelectVcr0x093MediaSelectTuner0x094Quit0x095Help0x096MediaSelectTape0x097MediaSelectSatellite0x098MediaSelectSecurity0x099MediaSelectHome0x09BMediaSelectHome0x09CChannelIncrement0x09CCahnnelDecrement0x09DCahnnelDecrement0x09EMediaSelectSap0x0A0VcrPlus0x0A1Once0x0A2Daily0x0A3Weekly0x0A4Monthly0x0B0Play0x0B1Pause0x0B2Record0x0B3FastForward0x0B4Rewind0x0B5ScanNextTrack0x0B6ScanPreviousTrack	0x08B	MediaDvd	
0x08EMediaVideoPhone0x08FMediaSelectGames0x090MediaSelectMessages0x091MediaSelectCd0x092MediaSelectVcr0x093MediaSelectTuner0x094Quit0x095Help0x096MediaSelectTape0x097MediaSelectCable0x098MediaSelectSecurity0x099MediaSelectSecurity0x09AMediaSelectCall0x09BMediaSelectCall0x09CChannelIncrement0x09DCahnnelDecrement0x09EMediaSelectSap0x0A0VcrPlus0x0A1Once0x0A2Daily0x0A3Weekly0x0A4Monthly0x0B0Play0x0B1Pause0x0B2Record0x0B3FastForward0x0B4Rewind0x0B5ScanNextTrack0x0B6ScanPreviousTrack	0x08C	MediaTelephone	
0x08F MediaSelectGames 0x090 MediaSelectMessages 0x091 MediaSelectCd 0x092 MediaSelectVcr 0x093 MediaSelectTuner 0x094 Quit 0x095 Help 0x096 MediaSelectTape 0x097 MediaSelectCable 0x098 MediaSelectSatellite 0x099 MediaSelectHome 0x090 MediaSelectCall 0x090 MediaSelectCall 0x090 ChannelIncrement 0x090 CahnnelDecrement 0x090 MediaSelectSap 0x040 VcrPlus 0x0A1 Once 0x0A2 Daily 0x0A3 Weekly 0x0A4 Monthly 0x0B0 Play 0x0B1 Pause 0x0B2 Record 0x0B3 FastForward 0x0B4 Rewind 0x0B5 ScanPreviousTrack	0x08D	MediaProgramGuide	
0x090 MediaSelectMessages 0x091 MediaSelectCd 0x092 MediaSelectVcr 0x093 MediaSelectTuner 0x094 Quit 0x095 Help 0x096 MediaSelectTape 0x097 MediaSelectCable 0x098 MediaSelectSatellite 0x099 MediaSelectSecurity 0x09A MediaSelectCall 0x09B MediaSelectCall 0x09C ChannelIncrement 0x09E MediaSelectSap 0x0A0 VcrPlus 0x0A1 Once 0x0A2 Daily 0x0A3 Weekly 0x0A4 Monthly 0x0B0 Play 0x0B1 Pause 0x0B2 Record 0x0B3 FastForward 0x0B4 Rewind 0x0B5 ScanPreviousTrack	0x08E		
0x091 MediaSelectCd 0x092 MediaSelectVcr 0x093 MediaSelectTuner 0x094 Quit 0x095 Help 0x096 MediaSelectTape 0x097 MediaSelectCable 0x098 MediaSelectSatellite 0x099 MediaSelectSecurity 0x09A MediaSelectCall 0x09B MediaSelectCall 0x09C ChannelIncrement 0x09E MediaSelectSap 0x0A0 VcrPlus 0x0A1 Once 0x0A2 Daily 0x0A3 Weekly 0x0A4 Monthly 0x0B0 Play 0x0B1 Pause 0x0B2 Record 0x0B3 FastForward 0x0B4 Rewind 0x0B5 ScanPreviousTrack	0x08F	MediaSelectGames	
0x092 MediaSelectVcr 0x093 MediaSelectTuner 0x094 Quit 0x095 Help 0x096 MediaSelectTape 0x097 MediaSelectCable 0x098 MediaSelectSecurity 0x099 MediaSelectSecurity 0x09A MediaSelectCall 0x09B MediaSelectCall 0x09C ChannelIncrement 0x09B MediaSelectSap 0x0A0 VcrPlus 0x0A1 Once 0x0A2 Daily 0x0A3 Weekly 0x0A4 Monthly 0x0B0 Play 0x0B1 Pause 0x0B2 Record 0x0B3 FastForward 0x0B4 Rewind 0x0B5 ScanNextTrack 0x0B6 ScanPreviousTrack	0x090	MediaSelectMessages	
0x093 MediaSelectTuner 0x094 Quit 0x095 Help 0x096 MediaSelectTape 0x097 MediaSelectCable 0x098 MediaSelectSatellite 0x099 MediaSelectSecurity 0x09A MediaSelectHome 0x09B MediaSelectCall 0x09C ChannelIncrement 0x09D CahnnelDecrement 0x09E MediaSelectSap 0x0A0 VcrPlus 0x0A1 Once 0x0A2 Daily 0x0A3 Weekly 0x0A4 Monthly 0x0B0 Play 0x0B1 Pause 0x0B2 Record 0x0B3 FastForward 0x0B4 Rewind 0x0B5 ScanPreviousTrack	0x091	MediaSelectCd	
0x094 Quit 0x095 Help 0x096 MediaSelectTape 0x097 MediaSelectCable 0x098 MediaSelectSatellite 0x099 MediaSelectHome 0x09A MediaSelectCall 0x09B MediaSelectCall 0x09C ChannelIncrement 0x09D CahnnelDecrement 0x09E MediaSelectSap 0x0A0 VcrPlus 0x0A1 Once 0x0A2 Daily 0x0A3 Weekly 0x0A4 Monthly 0x0B0 Play 0x0B1 Pause 0x0B2 Record 0x0B3 FastForward 0x0B4 Rewind 0x0B5 ScanNextTrack 0x0B6 ScanPreviousTrack	0x092	MediaSelectVcr	
0x095Help0x096MediaSelectTape0x097MediaSelectCable0x098MediaSelectSatellite0x099MediaSelectSecurity0x09AMediaSelectHome0x09BMediaSelectCall0x09CChannelIncrement0x09DCahnnelDecrement0x09EMediaSelectSap0x0A0VcrPlus0x0A1Once0x0A2Daily0x0A3Weekly0x0A4Monthly0x0B0Play0x0B1Pause0x0B2Record0x0B3FastForward0x0B4Rewind0x0B5ScanNextTrack0x0B6ScanPreviousTrack	0x093	MediaSelectTuner	
0x096MediaSelectTape0x097MediaSelectCable0x098MediaSelectSatellite0x099MediaSelectSecurity0x09AMediaSelectHome0x09BMediaSelectCall0x09CChannelIncrement0x09DCahnnelDecrement0x09EMediaSelectSap0x0A0VcrPlus0x0A1Once0x0A2Daily0x0A3Weekly0x0A4Monthly0x0B0Play0x0B1Pause0x0B2Record0x0B3FastForward0x0B4Rewind0x0B5ScanNextTrack0x0B6ScanPreviousTrack	0x094	Quit	
0x096MediaSelectTape0x097MediaSelectCable0x098MediaSelectSatellite0x099MediaSelectSecurity0x09AMediaSelectHome0x09BMediaSelectCall0x09CChannelIncrement0x09DCahnnelDecrement0x09EMediaSelectSap0x0A0VcrPlus0x0A1Once0x0A2Daily0x0A3Weekly0x0A4Monthly0x0B0Play0x0B1Pause0x0B2Record0x0B3FastForward0x0B4Rewind0x0B5ScanNextTrack0x0B6ScanPreviousTrack	0x095	Help	
0x098MediaSelectSatellite0x099MediaSelectSecurity0x09AMediaSelectHome0x09BMediaSelectCall0x09CChannelIncrement0x09DCahnnelDecrement0x09EMediaSelectSap0x0A0VcrPlus0x0A1Once0x0A2Daily0x0A3Weekly0x0A4Monthly0x0B0Play0x0B1Pause0x0B2Record0x0B3FastForward0x0B4Rewind0x0B5ScanNextTrack0x0B6ScanPreviousTrack	0x096		
0x099MediaSelectSecurity0x09AMediaSelectHome0x09BMediaSelectCall0x09CChannelIncrement0x09DCahnnelDecrement0x09EMediaSelectSap0x0A0VcrPlus0x0A1Once0x0A2Daily0x0A3Weekly0x0A4Monthly0x0B0Play0x0B1Pause0x0B2Record0x0B3FastForward0x0B4Rewind0x0B5ScanNextTrack0x0B6ScanPreviousTrack	0x097	MediaSelectCable	
0x09AMediaSelectHome0x09BMediaSelectCall0x09CChannelIncrement0x09DCahnnelDecrement0x09EMediaSelectSap0x0A0VcrPlus0x0A1Once0x0A2Daily0x0A3Weekly0x0A4Monthly0x0B0Play0x0B1Pause0x0B2Record0x0B3FastForward0x0B4Rewind0x0B5ScanNextTrack0x0B6ScanPreviousTrack	0x098	MediaSelectSatellite	
0x09BMediaSelectCall0x09CChannelIncrement0x09DCahnnelDecrement0x09EMediaSelectSap0x0A0VcrPlus0x0A1Once0x0A2Daily0x0A3Weekly0x0A4Monthly0x0B0Play0x0B1Pause0x0B2Record0x0B3FastForward0x0B4Rewind0x0B5ScanNextTrack0x0B6ScanPreviousTrack	0x099	MediaSelectSecurity	
0x09CChannelIncrement0x09DCahnnelDecrement0x09EMediaSelectSap0x0A0VcrPlus0x0A1Once0x0A2Daily0x0A3Weekly0x0A4Monthly0x0B0Play0x0B1Pause0x0B2Record0x0B3FastForward0x0B4Rewind0x0B5ScanNextTrack0x0B6ScanPreviousTrack	0x09A	MediaSelectHome	
0x09D CahnnelDecrement 0x09E MediaSelectSap 0x0A0 VcrPlus 0x0A1 Once 0x0A2 Daily 0x0A3 Weekly 0x0A4 Monthly 0x0B0 Play 0x0B1 Pause 0x0B2 Record 0x0B3 FastForward 0x0B4 Rewind 0x0B5 ScanNextTrack 0x0B6 ScanPreviousTrack	0x09B	MediaSelectCall	
0x09E MediaSelectSap 0x0A0 VcrPlus 0x0A1 Once 0x0A2 Daily 0x0A3 Weekly 0x0A4 Monthly 0x0B0 Play 0x0B1 Pause 0x0B2 Record 0x0B3 FastForward 0x0B4 Rewind 0x0B5 ScanNextTrack 0x0B6 ScanPreviousTrack	0x09C	ChannelIncrement	
0x0A0 VcrPlus 0x0A1 Once 0x0A2 Daily 0x0A3 Weekly 0x0A4 Monthly 0x0B0 Play 0x0B1 Pause 0x0B2 Record 0x0B3 FastForward 0x0B4 Rewind 0x0B5 ScanNextTrack 0x0B6 ScanPreviousTrack	0x09D	CahnnelDecrement	
0x0A1 Once 0x0A2 Daily 0x0A3 Weekly 0x0A4 Monthly 0x0B0 Play 0x0B1 Pause 0x0B2 Record 0x0B3 FastForward 0x0B4 Rewind 0x0B5 ScanNextTrack 0x0B6 ScanPreviousTrack	0x09E	MediaSelectSap	
0x0A2 Daily 0x0A3 Weekly 0x0A4 Monthly 0x0B0 Play 0x0B1 Pause 0x0B2 Record 0x0B3 FastForward 0x0B4 Rewind 0x0B5 ScanNextTrack 0x0B6 ScanPreviousTrack	0x0A0	VcrPlus	
0x0A3 Weekly 0x0A4 Monthly 0x0B0 Play 0x0B1 Pause 0x0B2 Record 0x0B3 FastForward 0x0B4 Rewind 0x0B5 ScanNextTrack 0x0B6 ScanPreviousTrack	0x0A1	Once	
0x0A4 Monthly 0x0B0 Play 0x0B1 Pause 0x0B2 Record 0x0B3 FastForward 0x0B4 Rewind 0x0B5 ScanNextTrack 0x0B6 ScanPreviousTrack	0x0A2	Daily	
0x0B0 Play 0x0B1 Pause 0x0B2 Record 0x0B3 FastForward 0x0B4 Rewind 0x0B5 ScanNextTrack 0x0B6 ScanPreviousTrack	0x0A3	Weekly	
0x0B1 Pause 0x0B2 Record 0x0B3 FastForward 0x0B4 Rewind 0x0B5 ScanNextTrack 0x0B6 ScanPreviousTrack	0x0A4	Monthly	
0x0B2Record0x0B3FastForward0x0B4Rewind0x0B5ScanNextTrack0x0B6ScanPreviousTrack	0x0B0	Play	
0x0B3FastForward0x0B4Rewind0x0B5ScanNextTrack0x0B6ScanPreviousTrack	0x0B1	Pause	
0x0B4Rewind0x0B5ScanNextTrack0x0B6ScanPreviousTrack	0x0B2	Record	
0x0B5 ScanNextTrack 0x0B6 ScanPreviousTrack	0x0B3	FastForward	
0x0B6 ScanPreviousTrack	0x0B4	Rewind	
	0x0B5	ScanNextTrack	
0x0B7 Stop	0x0B6	ScanPreviousTrack	
	0x0B7	Stop	



0x0B8	Figet	1
0x0B9	Eject RandomPlay	
0x0B9 0x0BC	Repeat	
0x0BE	TrackNormal	
0x0C0	FrameForward	
0x0C0 0x0C1	FrameBack	
0x0C1 0x0C2	Mark	
0x0C2 0x0C3	ClearMark	
0x0C3 0x0C4	RepeatFromMark	
0x0C4 0x0C5	ReturnToMark	
0x0C5	SearchMarkForwards	
0x0C0 0x0C7	SearchMarkBackwards	
0x0C7 0x0C8	CounterReset	
0x0C9	ShowCounter	
0x0C9 0x0CA	TrackingIncrement	
0x0CA 0x0CB	TrackingDecrement	
0x0CD 0x0CC	StopEject	
0x0CD	PausePlay	
0x0CE	PlaySkip	
0x0E2	Mute	
0x0E5	BassBoost	
0x0E6	SurroundMode	
0x0E7	Loudness	
0x0E8	Mpx	
0x0E9	VolumeUp	
0x0EA	VolumeDown	
0x0F0	SpeedSelect	
0x0F2	StandardPlay	
0x0F3	LongPlay	
0x0F4	ExtendedPlay	
0x0F5	Slow	
0x100	FanEnable	
0x102	LightEnable	
0x104	ClimateControlEnable	
0x106	SecurityEnable	
0x107	FireAlarm	
0x10A	Motion	
0x10B	DuressAlarm	
0x10C	HoldupAlarm	
0x10D	MedicalAlarm	
0x150	BalanceRight	
0x151	BalanceLeft	
		I



0-150	D lo	
0x152	BassIncr	
0x153	BassDecr	
0x154	TrebleIncr	
0x155	TrebleDecr	
0x171	SubChannelIncrement	
0x172	SubChannelDecrement	
0x173	AltAudioIncrement	
0x174	AltAudioDecrement	
0x181	LaunchButtonConfigTool	
0x182	ProgrammableButtonConfig	
0x183	ConsumerControlConfig	
0x184	WordProcessor	
0x185	TextEditor	
0x186	Spreadsheet	
0x187	GraphicsEditor	
0x188	PresentationApp	
0x189	DatabaseApp	
0x18A	EmailReader	
0x18B	Newsreader	
0x18C	Voicemail	
0x18D	ContactsAddressBook	
0x18E	CalendarSchedule	
0x18F	TaskProjectManager	
0x190	LogJournalTimecard	
0x191	CheckbookFinance	
0x192	Calculator	
0x193	aVCapturePlayback	
0x194	LocalMachineBrowser	
0x195	LanWanBrowser	
0x196	InternetBrowser	
0x197	RemoteNetworkingIspConnect	
0x198	NetworkConference	
0x199	NetworkChat	
0x19A	TelephonyDialer	
0x19B	Logon	
0x19C	Logoff	
0x19D	LogonLogoff	
0x19E	TerminalLockScreensaver	
0x19F	ControlPanel	
0x1A0	CommandLineProcessorRun	
0x1A1	ProcessTaskManager	
0x1A2	SelectTastApp	



0x1A3	NextTaskApp	
0x1A4	PreviousTaskApp	
0x1A5	PreemptiveHaltTaskApp	
0x1A6	IntegratedHelpCenter	
0x1A7	Documents	
0x1A8	Thesaurus	
0x1A9	Dictionary	
0x1AA	Desktop	
0x1AB	SpellCheck	
0x1AC	GrammarCheck	
0x1AD	WirelessStatus	
0x1AE	KeyboardLayout	
0x1AF	VirusProtection	
0x1B0	Encryption	
0x1B1	ScreenSaver	
0x1B2	Alarms	
0x1B3	Clock	
0x1B4	FileBrowser	
0x1B5	PowerStatus	
0x1B6	ImageBrowser	
0x1B7	AudioBrowser	
0x1B8	MovieBrowser	
0x1B9	DigitalRightsManager	
0x1BA	DigitalWallet	
0x1BC	InstantMessaging	
0x1BD	OemFeaturesTipsTutorial	
0x1BE	OemHelp	
0x1BF	OnlineCommunity .	
0x1C0	EntertainmentContent	
0x1C1	OnlineShopping	
0x1C2	SmartcardInfoHelp	
0x1C3	MarketMonitor	
0x1C4	CustomizedCorpNews	
0x1C5	OnlineActivity	
0x1C6	SearchBrowser	
0x1C7	AudioPlayer	
0x201	New	
0x202	Open	
0x203	Close	
0x204	Exit	
0x205	Maximize	
0x206	Minimize	
J		



0x207	Save
0x208	Print
0x209	Properties
0x21A	Undo
0x21B	Сору
0x21C	Cut
0x21D	Paste
0x21E	SelectAll
0x21F	Find
0x220	FindAndReplace
0x221	Search
0x222	GoTo
0x223	Home
0x224	Back
0x225	Forward
0x226	Stop
0x227	Refresh
0x228	PreviousLink
0x229	NextLink
0x22A	Bookmarks
0x22B	History
0x22C	Subscriptions
0x22D	ZoomIn
0x22E	ZoomOut
0x22F	Zoom
0x230	FullScreenView
0x231	NormalView
0x232	ViewToggle
0x233	ScrollUp
0x234	ScrollDown
0x235	Scroll
0x236	PanLeft
0x237	PanRight
0x238	Pan
0x239	NewWindow
0x23A	TileHorizontally
0x23B	TileVertically
0x23C	Format
0x23D	Edit
0x23E	Bold
0x23F	Italics
0x240	Underline



0x241	Strikethrough	
0x242		
	Subscript	
0x243	Superscript	
0x244	AllCaps	
0x245	Rotate	
0x246	Resize	
0x247	FilpHorizontal	
	· •	
0x248	FilpVertical	
0x249	MirrorHorizontal	
0x24A	MirrorVertical	
0x24B	FontSelect	
0x24C	FontColor	
0x24D	FontSize	
0x24E		
	JustifyLeft	
0x24F	JustifyCenterH	
0x250	JustifyRight	
0x251	JustifyBlockH	
0x252	JustifyTop	
0x253	JustifyCenterV	
0x254	JustifyBottom	
0x255	JustifyBlockV	
0x256	IndentDecrease	
0x257	IndentIncrease	
0x258	NumberedList	
0x259	RestartNumbering	
0x25A	BulletedList	
0x25B	Promote	
0x25C	Demote	
0x25C	Yes	
0x25E	No	
0x25F	Cancel	
0x260	Catalog	
0x261	BuyCheckout	
0x262	AddToCart	
0x263	Expand	
0x264		
	ExpandAll	
0x265	Collapse	
0x266	CollapseAll	
0x267	PrintPreview	
0x268	PasteSpecial	
0x269	InsertMode	
0x26A	Delete	
ONZON	Delete	



0x26B	Lock		
0x26C			
	Unlock		
0x26D	Protect		
0x26E	Unprotect		
0x26F	AttachComment		
0x270	DeleteComment		
0x271	ViewComment		
0x272	SelectWord		
0x273	SelectSentence		
0x274	SelectParagraph		
0x275	SelectColumn		
0x276	SelectRow		
0x277	SelectTable		
0x278	SelectObject		
0x279	RedoRepeat		
0x27A	Sort		
0x27B	SortAscending		
0x27C	SortDescending		
0x27D	Filter		
0x27E	SetClock		
0x27F	ViewClock		
0x280	SelectTimeZone		
0x281	EditTimeZone		
0x282	SetAlarm		
0x283	ClearAlarm		
0x284	SnoozeAlarm		
0x285	ResetAlarm		
0x286	Synchronize		
0x287	SendReceive		
0x288	SendTo		
0x289	Reply		
0x28A	ReplyAll		
0x28B	ForwardMsg		
0x28C	Send		
0x28D	AttachFile		
0x28E	Upload		
0x28F	Download		
0x290	SetBorders		
0x291	InsertRow		
0x292	InsertColumn		
0x292 0x293	InsertFile		
0x294	InsertPicture		



InsertObject	0x295
InsertSymbol	0x296
SaveAndClose	0x297
Rename	0x298
Merge	0x299
Split	0x29A
DistributeHorizontally	0x29B
DistributeVertically	0x29C
NextKeyboardLayoutSelect	0x29D



13 LED Indicator Code Table

Following is a table LED Indicator Codes defined by the USB HID Spec. On most OSs only NumLock, ScrollLock and CapsLock are used. Even if the keyboard supports all of the LED Indicator Codes, unless the OS supports it, you will not be able to use it.

For completeness, the entire table is listed here.

Table 13.1: Table of USB LED Indicator Codes

Indicator Code	Name	Alternate Name(s)
0x01 (1)	NumLock	Num
0x02 (2)	CapsLock	Caps
0x03 (3)	ScrollLock	Scroll
0x04 (4)	Compose	
0x05 (5)	Kana	
0x06 (6)	Power	
0x07 (7)	Shift	
0x08 (8)	DoNotDisturb	
0x09 (9)	Mute	
0x0A (10)	ToneEnable	
0x0B (11)	HighcutFilter	
0x0C (12)	LowcutFilter	
0x0D (13)	EqlEnable	
0x0E (14)	SndFldOn	
0x0F (15)	SurroundOn	
0x10 (16)	Repeat	
0x11 (17)	Stereo	
0x12 (18)	SampleRtDet	
0x13 (19)	Spinning	
0x14 (20)	Cav	
0x15 (21)	Clv	
0x16 (22)	RecFmtDet	
0x17 (23)	OffHook	
0x18 (24)	Ring	
0x19 (25)	MsgWaiting	
0x1A (26)	DataMode	
0x1B (27)	BatOperation	
0x1C (28)	BatOk	
0x1D (29)	BatLow	
0x1E (30)	Speaker	



0x1F (31)	HeadSet
0x20 (32)	Hold
0x21 (33)	Microphone
0x22 (34)	Coverage
0x23 (35)	NightMode
0x24 (36)	SendCalls
0x25 (37)	CallPickup
0x26 (38)	Conference
0x27 (39)	StandBy
0x28 (40)	CameraOn
0x29 (41)	CameraOff
, ,	
0x2A (42)	OnLine
0x2B (43)	OffLine
0x2C (44)	Busy
0x2D (45)	Ready
0x2E (46)	PaperOut
0x2F (47)	PaperJam
0x30 (48)	Remote
0x31 (49)	Forward
0x32 (50)	Reverse
0x33 (51)	Stop
0x34 (52)	Rewind
0x35 (53)	FastForward
0x36 (54)	Play
	_
0x37 (55)	Pause
0x38 (56)	Record
0x39 (57)	Error
0x3A (58)	Usi
0x3B (59)	Uiui
0x3C (60)	Ummi
0x3D (61)	IndOn
0x3E (62)	IndFlash
0x3F (63)	IndSlowBlnk
0x40 (64)	IndFastBlnk
0x40 (64)	IndOff
0x41 (03) 0x42 (66)	FlashOnTime
0x43 (67)	SlwBOnTime
0x44 (68)	SlwBOffTime
0x45 (69)	FstBOnTime
0x46 (70)	FstBOffTime
0x47 (71)	Uic
0x48 (72)	IndRed
- · ·	I



0x49 (73)	IndGreen	
0x4A (74)	IndAmber	
0x4B (75)	GenericInd	
0x4C (76)	SysSuspend	
0x4D (77)	ExtPwrConn	



14 Capabilities Table

Following is a table of common capabilities. Whenever defining new capabilities, make sure to check this table to make sure there are no namespace clashes. The number beside each of the arguments specifies the size of the argument in bytes (e.g. $2 \Rightarrow 16$ bits).

Table 14.1: Table of Common Capabilities

Capability	Function	Argument(s)
consCtrlOut	Output_consCtrlSend_capability	consCode : 2
kbdProtocolBoot	Output_kbdProtocolBoot_capability	
kbdProtocolNKRO	Output_kbdProtocolNKRO_capability	
layerLatch	Macro_layerLatch_capability	layer : 2
layerLock	Macro_layerLock_capability	layer : 2
layerShift	Macro_layerShift_capability	layer : 2
layerState	Macro_layerState_capability	layer: 2, state: 1
noneOut	Output_noneSend_capability	
sysCtrlOut	Output_sysCtrlSend_capability	sysCode : 1
usbKeyOut	Output_usbCodeSend_capability	usbCode : 1



15 Glossary

- **Fall-through** When a key is undefined on a particular layer, the key definition on the previously stacked layer will be used. Eventually the key definition will be set to using the default layer. If the None keyword is used, then the fall-through will stop and no action will take place.
- **Latch** When referring to keyboards, a key function that is only enabled until the release of the next keypress.
- **Lock** When referring to keyboards, a key function that is enabled until that key is pressed again (e.g. Caps Lock).
- **NKRO** N-Key Rollover is the capability to press N number of keys at the same time on a keyboard and have them all register on the OS simultaneously.
- **Scan Code** Row x Column code or native protocol code used by the keyboard.
- **Shift** When referring to keyboards, a key function that is enabled while that key is held.
- **USB Code** Keyboard Press/Release codes as defined by the USB HID Spec.



16 Future Considerations

Possible features for future revisions of the KLL spec. If the feature is in this list, there is no guarantee that it will be in the specified version series.

16.1 Possible 0.6+

- Internal lock/state variables (Virtual States)
- Add capabilities descriptions
- Mouse control
- Joystick control
- Unicode output
- More concise way to indicate capability defaults
- Add field to change USB country code
- Analog velocity and acceleration detection (optional, depends on hardware)
- Add debounce time control